

```

/**
 * Marlin 3D Printer Firmware
 * Copyright (c) 2020 MarlinFirmware [https://github.com/MarlinFirmware/Marlin]
 *
 * Based on Sprinter and grbl.
 * Copyright (c) 2011 Camiel Gubbels / Erik van der Zalm
 *
 * This program is free software: you can redistribute it and/or modify
 * it under the terms of the GNU General Public License as published by
 * the Free Software Foundation, either version 3 of the License, or
 * (at your option) any later version.
 *
 * This program is distributed in the hope that it will be useful,
 * but WITHOUT ANY WARRANTY; without even the implied warranty of
 * MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the
 * GNU General Public License for more details.
 *
 * You should have received a copy of the GNU General Public License
 * along with this program. If not, see <https://www.gnu.org/licenses/>.
 */
#pragma once

/**
 * Configuration.h
 *
 * Basic settings such as:
 *
 * - Type of electronics
 * - Type of temperature sensor
 * - Printer geometry
 * - Endstop configuration
 * - LCD controller
 * - Extra features
 *
 * Advanced settings can be found in Configuration_adv.h
 */
#define CONFIGURATION_H_VERSION 020008

//
=====
==
//===== Getting Started =====
//
=====
==

/**
 * Here are some useful links to help get your machine configured and calibrated:
 *
 * Example Configs:  https://github.com/MarlinFirmware/Configurations/branches/all
 *
 * Průša Calculator:  https://blog.prusaprinters.org/calculator_3416/
 *
 * Calibration Guides: https://reprap.org/wiki/Calibration
 *                      https://reprap.org/wiki/Triffid_Hunter%27s_Calibration_Guide
 *                      https://sites.google.com/site/repraplogphase/calibration-of-your-reprap
 *                      https://youtu.be/wAL9d7Fglnk
 *
 * Calibration Objects: https://www.thingiverse.com/thing:5573

```

```

*           https://www.thingiverse.com/thing:1278865
*/

//
=====
==
//===== DELTA / SCARA / TPARA =====
//
=====
==
//
// Download configurations from the link above and customize for your machine.
// Examples are located in config/examples/delta, .../SCARA, and .../TPARA.
//
//
=====
==

// @section info

// Author info of this build printed to the host during boot and M115
#define STRING_CONFIG_H_AUTHOR "Peter Jordan 210326 SKR 1.4 Turbo" // Who made the
changes.
//#define CUSTOM_VERSION_FILE Version.h // Path from the root directory (no quotes)

/**
 * *** VENDORS PLEASE READ ***
 *
 * Marlin allows you to add a custom boot image for Graphical LCDs.
 * With this option Marlin will first show your custom screen followed
 * by the standard Marlin logo with version number and web URL.
 *
 * We encourage you to take advantage of this new feature and we also
 * respectfully request that you retain the unmodified Marlin boot screen.
 */

// Show the Marlin bootscreen on startup. ** ENABLE FOR PRODUCTION **
#define SHOW_BOOTSCREEN

// Show the bitmap in Marlin/_Bootscreen.h on startup.
//#define SHOW_CUSTOM_BOOTSCREEN

// Show the bitmap in Marlin/_Statusscreen.h on the status screen.
//#define CUSTOM_STATUS_SCREEN_IMAGE

// @section machine

/**
 * Select the serial port on the board to use for communication with the host.
 * This allows the connection of wireless adapters (for instance) to non-default port pins.
 * Serial port -1 is the USB emulated serial port, if available.
 * Note: The first serial port (-1 or 0) will always be used by the Arduino bootloader.
 *
 * :[-1, 0, 1, 2, 3, 4, 5, 6, 7]
 */
#define SERIAL_PORT -1

/**
 * Select a secondary serial port on the board to use for communication with the host.
 * Currently Ethernet (-2) is only supported on Teensy 4.1 boards.

```

```

* :[-2, -1, 0, 1, 2, 3, 4, 5, 6, 7]
*/
#define SERIAL_PORT_2 -0

/**
 * This setting determines the communication speed of the printer.
 *
 * 250000 works in most cases, but you might try a lower speed if
 * you commonly experience drop-outs during host printing.
 * You may try up to 1000000 to speed up SD file transfer.
 *
 * :[2400, 9600, 19200, 38400, 57600, 115200, 250000, 500000, 1000000]
 */
#define BAUDRATE 250000

// Enable the Bluetooth serial interface on AT90USB devices
//#define BLUETOOTH

// Choose the name from boards.h that matches your setup
#ifndef MOTHERBOARD
  #define MOTHERBOARD BOARD_BTT_SKR_V1_4_TURBO
#endif

// Name displayed in the LCD "Ready" message and Info menu
#define CUSTOM_MACHINE_NAME "Jordan 410"

// Printer's unique ID, used by some programs to differentiate between machines.
// Choose your own or use a service like https://www.uuidgenerator.net/version4
//#define MACHINE_UUID "00000000-0000-0000-0000-000000000000"

// @section extruder

// This defines the number of extruders
// :[0, 1, 2, 3, 4, 5, 6, 7, 8]
#define EXTRUDERS 1

// Generally expected filament diameter (1.75, 2.85, 3.0, ...). Used for Volumetric, Filament Width
// Sensor, etc.
#define DEFAULT_NOMINAL_FILAMENT_DIA 1.75

// For Cyclops or any "multi-extruder" that shares a single nozzle.
//#define SINGLENOZZLE

// Save and restore temperature and fan speed on tool-change.
// Set standby for the unselected tool with M104/106/109 T...
#if ENABLED(SINGLENOZZLE)
  //#define SINGLENOZZLE_STANDBY_TEMP
  //#define SINGLENOZZLE_STANDBY_FAN
#endif

/**
 * Multi-Material Unit
 * Set to one of these predefined models:
 *
 * PRUSA_MMU1      : Průša MMU1 (The "multiplexer" version)
 * PRUSA_MMU2      : Průša MMU2
 * PRUSA_MMU2S     : Průša MMU2S (Requires MK3S extruder with motion sensor,
EXTRUDERS = 5)
 * SMUFF_EMU_MMU2  : Technik Gegg SMuFF (Průša MMU2 emulation mode)
 * SMUFF_EMU_MMU2S : Technik Gegg SMuFF (Průša MMU2S emulation mode)

```

```

*
* Requires NOZZLE_PARK_FEATURE to park print head in case MMU unit fails.
* See additional options in Configuration_adv.h.
*/
//#define MMU_MODEL PRUSA_MMU2

// A dual extruder that uses a single stepper motor
//#define SWITCHING_EXTRUDER
#if ENABLED(SWITCHING_EXTRUDER)
  #define SWITCHING_EXTRUDER_SERVO_NR 0
  #define SWITCHING_EXTRUDER_SERVO_ANGLES { 0, 90 } // Angles for E0, E1[, E2, E3]
  #if EXTRUDERS > 3
    #define SWITCHING_EXTRUDER_E23_SERVO_NR 1
  #endif
#endif

// A dual-nozzle that uses a servomotor to raise/lower one (or both) of the nozzles
//#define SWITCHING_NOZZLE
#if ENABLED(SWITCHING_NOZZLE)
  #define SWITCHING_NOZZLE_SERVO_NR 0
  //#define SWITCHING_NOZZLE_E1_SERVO_NR 1 // If two servos are used, the index of
the second
  #define SWITCHING_NOZZLE_SERVO_ANGLES { 0, 90 } // Angles for E0, E1 (single servo) or
lowered/raised (dual servo)
#endif

/**
 * Two separate X-carriages with extruders that connect to a moving part
 * via a solenoid docking mechanism. Requires SOL1_PIN and SOL2_PIN.
 */
//#define PARKING_EXTRUDER

/**
 * Two separate X-carriages with extruders that connect to a moving part
 * via a magnetic docking mechanism using movements and no solenoid
 *
 * project : https://www.thingiverse.com/thing:3080893
 * movements : https://youtu.be/0xCEiG9VS3k
 * https://youtu.be/BqbcS0CU2FE
 */
//#define MAGNETIC_PARKING_EXTRUDER

#if EITHER(PARKING_EXTRUDER, MAGNETIC_PARKING_EXTRUDER)

  #define PARKING_EXTRUDER_PARKING_X { -78, 184 } // X positions for parking the
extruders
  #define PARKING_EXTRUDER_GRAB_DISTANCE 1 // (mm) Distance to move beyond the
parking point to grab the extruder
  //#define MANUAL_SOLENOID_CONTROL // Manual control of docking solenoids
with M380 S / M381

  #if ENABLED(PARKING_EXTRUDER)

    #define PARKING_EXTRUDER_SOLENOIDS_INVERT // If enabled, the solenoid is NOT
magnetized with applied voltage
    #define PARKING_EXTRUDER_SOLENOIDS_PINS_ACTIVE LOW // LOW or HIGH pin signal
energizes the coil
    #define PARKING_EXTRUDER_SOLENOIDS_DELAY 250 // (ms) Delay for magnetic field.
No delay if 0 or not defined.

```

```

    //#define MANUAL_SOLENOID_CONTROL           // Manual control of docking solenoids
with M380 S / M381

    #elif ENABLED(MAGNETIC_PARKING_EXTRUDER)

        #define MPE_FAST_SPEED    9000    // (mm/min) Speed for travel before last distance point
        #define MPE_SLOW_SPEED    4500    // (mm/min) Speed for last distance travel to park and
couple
        #define MPE_TRAVEL_DISTANCE 10    // (mm) Last distance point
        #define MPE_COMPENSATION  0    // Offset Compensation -1 , 0 , 1 (multiplier) only for
coupling

    #endif

#endif

/**
 * Switching Toolhead
 *
 * Support for swappable and dockable toolheads, such as
 * the E3D Tool Changer. Toolheads are locked with a servo.
 */
//#define SWITCHING_TOOLHEAD

/**
 * Magnetic Switching Toolhead
 *
 * Support swappable and dockable toolheads with a magnetic
 * docking mechanism using movement and no servo.
 */
//#define MAGNETIC_SWITCHING_TOOLHEAD

/**
 * Electromagnetic Switching Toolhead
 *
 * Parking for CoreXY / HBot kinematics.
 * Toolheads are parked at one edge and held with an electromagnet.
 * Supports more than 2 Toolheads. See https://youtu.be/JolbsAKTKf4
 */
//#define ELECTROMAGNETIC_SWITCHING_TOOLHEAD

#if ANY(SWITCHING_TOOLHEAD, MAGNETIC_SWITCHING_TOOLHEAD,
ELECTROMAGNETIC_SWITCHING_TOOLHEAD)
    #define SWITCHING_TOOLHEAD_Y_POS    235    // (mm) Y position of the toolhead dock
    #define SWITCHING_TOOLHEAD_Y_SECURITY 10    // (mm) Security distance Y axis
    #define SWITCHING_TOOLHEAD_Y_CLEAR  60    // (mm) Minimum distance from dock
for unobstructed X axis
    #define SWITCHING_TOOLHEAD_X_POS    { 215, 0 } // (mm) X positions for parking the
extruders
    #if ENABLED(SWITCHING_TOOLHEAD)
        #define SWITCHING_TOOLHEAD_SERVO_NR 2    // Index of the servo connector
        #define SWITCHING_TOOLHEAD_SERVO_ANGLES { 0, 180 } // (degrees) Angles for Lock,
Unlock
    #elif ENABLED(MAGNETIC_SWITCHING_TOOLHEAD)
        #define SWITCHING_TOOLHEAD_Y_RELEASE 5    // (mm) Security distance Y axis
        #define SWITCHING_TOOLHEAD_X_SECURITY { 90, 150 } // (mm) Security distance X axis
(T0,T1)
        //#define PRIME_BEFORE_REMOVE           // Prime the nozzle before release from the
dock
        #if ENABLED(PRIME_BEFORE_REMOVE)

```

```

    #define SWITCHING_TOOLHEAD_PRIME_MM      20 // (mm) Extruder prime length
    #define SWITCHING_TOOLHEAD_RETRACT_MM   10 // (mm) Retract after priming
length
    #define SWITCHING_TOOLHEAD_PRIME_FEEDRATE 300 // (mm/min) Extruder prime
feedrate
    #define SWITCHING_TOOLHEAD_RETRACT_FEEDRATE 2400 // (mm/min) Extruder retract
feedrate
    #endif
    #elif ENABLED(ELECTROMAGNETIC_SWITCHING_TOOLHEAD)
    #define SWITCHING_TOOLHEAD_Z_HOP        2 // (mm) Z raise for switching
    #endif
#endif

/**
 * "Mixing Extruder"
 * - Adds G-codes M163 and M164 to set and "commit" the current mix factors.
 * - Extends the stepping routines to move multiple steppers in proportion to the mix.
 * - Optional support for Repetier Firmware's 'M164 S<index>' supporting virtual tools.
 * - This implementation supports up to two mixing extruders.
 * - Enable DIRECT_MIXING_IN_G1 for M165 and mixing in G1 (from Pia Taubert's reference
implementation).
 */
##define MIXING_EXTRUDER
#if ENABLED(MIXING_EXTRUDER)
    #define MIXING_STEPPERS 2 // Number of steppers in your mixing extruder
    #define MIXING_VIRTUAL_TOOLS 16 // Use the Virtual Tool method with M163 and M164
    ##define DIRECT_MIXING_IN_G1 // Allow ABCDHI mix factors in G1 movement commands
    ##define GRADIENT_MIX // Support for gradient mixing with M166 and LCD
    #if ENABLED(GRADIENT_MIX)
        ##define GRADIENT_VTOOL // Add M166 T to use a V-tool index as a Gradient alias
    #endif
#endif

// Offset of the extruders (uncomment if using more than one and relying on firmware to position
when changing).
// The offset has to be X=0, Y=0 for the extruder 0 hotend (default extruder).
// For the other hotends it is their distance from the extruder 0 hotend.
##define HOTEND_OFFSET_X { 0.0, 20.00 } // (mm) relative X-offset for each nozzle
##define HOTEND_OFFSET_Y { 0.0, 5.00 } // (mm) relative Y-offset for each nozzle
##define HOTEND_OFFSET_Z { 0.0, 0.00 } // (mm) relative Z-offset for each nozzle

// @section machine

/**
 * Power Supply Control
 *
 * Enable and connect the power supply to the PS_ON_PIN.
 * Specify whether the power supply is active HIGH or active LOW.
 */
##define PSU_CONTROL
##define PSU_NAME "Power Supply"

#if ENABLED(PSU_CONTROL)
    #define PSU_ACTIVE_STATE LOW // Set 'LOW' for ATX, 'HIGH' for X-Box

    ##define PSU_DEFAULT_OFF // Keep power off until enabled directly with M80
    ##define PSU_POWERUP_DELAY 250 // (ms) Delay for the PSU to warm up to full power

    ##define PSU_POWERUP_GCODE "M355 S1" // G-code to run after power-on (e.g., case light
on)

```

```

// #define PSU_POWEROFF_GCODE "M355 S0" // G-code to run before power-off (e.g., case
light off)

// #define AUTO_POWER_CONTROL // Enable automatic control of the PS_ON pin
# if ENABLED(AUTO_POWER_CONTROL)
# define AUTO_POWER_FANS // Turn on PSU if fans need power
# define AUTO_POWER_E_FANS
# define AUTO_POWER_CONTROLLERFAN
# define AUTO_POWER_CHAMBER_FAN
# define AUTO_POWER_COOLER_FAN
// #define AUTO_POWER_E_TEMP 50 // (°C) Turn on PSU if any extruder is over this
temperature
// #define AUTO_POWER_CHAMBER_TEMP 30 // (°C) Turn on PSU if the chamber is over this
temperature
// #define AUTO_POWER_COOLER_TEMP 26 // (°C) Turn on PSU if the cooler is over this
temperature
# define POWER_TIMEOUT 30 // (s) Turn off power if the machine is idle for this
duration
// #define POWER_OFF_DELAY 60 // (s) Delay of poweroff after M81 command. Useful to
let fans run for extra time.
# endif
# endif

//
=====
==
// ===== Thermal Settings =====
//
=====
==
// @section temperature

/**
 * --NORMAL IS 4.7kohm PULLUP!-- 1kohm pullup can be used on hotend sensor, using correct
resistor and table
 *
 * Temperature sensors available:
 *
 * -5 : PT100 / PT1000 with MAX31865 (only for sensors 0-1)
 * -3 : thermocouple with MAX31855 (only for sensors 0-1)
 * -2 : thermocouple with MAX6675 (only for sensors 0-1)
 * -4 : thermocouple with AD8495
 * -1 : thermocouple with AD595
 * 0 : not used
 * 1 : 100k thermistor - best choice for EPCOS 100k (4.7k pullup)
 * 331 : (3.3V scaled thermistor 1 table for MEGA)
 * 332 : (3.3V scaled thermistor 1 table for DUE)
 * 2 : 200k thermistor - ATC Semitec 204GT-2 (4.7k pullup)
 * 202 : 200k thermistor - Copymaster 3D
 * 3 : Mendel-parts thermistor (4.7k pullup)
 * 4 : 10k thermistor !! do not use it for a hotend. It gives bad resolution at high temp. !!
 * 5 : 100K thermistor - ATC Semitec 104GT-2/104NT-4-R025H42G (Used in ParCan, J-Head,
and E3D) (4.7k pullup)
 * 501 : 100K Zonestar (Tronxy X3A) Thermistor
 * 502 : 100K Zonestar Thermistor used by hot bed in Zonestar Průša P802M
 * 512 : 100k RPW-Ultra hotend thermistor (4.7k pullup)
 * 6 : 100k EPCOS - Not as accurate as table 1 (created using a fluke thermocouple) (4.7k
pullup)
 * 7 : 100k Honeywell thermistor 135-104LAG-J01 (4.7k pullup)
 * 71 : 100k Honeywell thermistor 135-104LAF-J01 (4.7k pullup)

```

- * 8 : 100k 0603 SMD Vishay NTCS0603E3104FXT (4.7k pullup)
- * 9 : 100k GE Sensing AL03006-58.2K-97-G1 (4.7k pullup)
- * 10 : 100k RS thermistor 198-961 (4.7k pullup)
- * 11 : 100k beta 3950 1% thermistor (Used in Keenovo AC silicone mats and most Wanhao i3 machines) (4.7k pullup)
- * 12 : 100k 0603 SMD Vishay NTCS0603E3104FXT (4.7k pullup) (calibrated for Makibox hot bed)
- * 13 : 100k Hisens 3950 1% up to 300°C for hotend "Simple ONE " & "Hotend "All In ONE"
- * 15 : 100k thermistor calibration for JGAurora A5 hotend
- * 18 : ATC Semitec 204GT-2 (4.7k pullup) Dagoma.Fr - MKS_Base_DKU001327
- * 20 : Pt100 with circuit in the Ultimainboard V2.x with mainboard ADC reference voltage = INA826 amplifier-board supply voltage.
- * NOTES: (1) Must use an ADC input with no pullup. (2) Some INA826 amplifiers are unreliable at 3.3V so consider using sensor 147, 110, or 21.
- * 21 : Pt100 with circuit in the Ultimainboard V2.x with 3.3v ADC reference voltage (STM32, LPC176x...) and 5V INA826 amplifier board supply.
- * NOTE: ADC pins are not 5V tolerant. Not recommended because it's possible to damage the CPU by going over 500°C.
- * 22 : 100k (hotend) with 4.7k pullup to 3.3V and 220R to analog input (as in GTM32 Pro vB)
- * 23 : 100k (bed) with 4.7k pullup to 3.3v and 220R to analog input (as in GTM32 Pro vB)
- * 30 : Kis3d Silicone heating mat 200W/300W with 6mm precision cast plate (EN AW 5083) NTC100K / B3950 (4.7k pullup)
- * 201 : Pt100 with circuit in Overlord, similar to Ultimainboard V2.x
- * 60 : 100k Maker's Tool Works Kapton Bed Thermistor beta=3950
- * 61 : 100k Formbot / Vivedino 3950 350C thermistor 4.7k pullup
- * 66 : 4.7M High Temperature thermistor from Dyze Design
- * 67 : 450C thermistor from SliceEngineering
- * 70 : the 100K thermistor found in the bq Hephestos 2
- * 75 : 100k Generic Silicon Heat Pad with NTC 100K MGB18-104F39050L32 thermistor
- * 99 : 100k thermistor with a 10K pull-up resistor (found on some Wanhao i3 machines)
- * 1k ohm pullup tables - This is atypical, and requires changing out the 4.7k pullup for 1k. (but gives greater accuracy and more stable PID)
- * 51 : 100k thermistor - EPCOS (1k pullup)
- * 52 : 200k thermistor - ATC Semitec 204GT-2 (1k pullup)
- * 55 : 100k thermistor - ATC Semitec 104GT-2 (Used in ParCan & J-Head) (1k pullup)
- * 1047 : Pt1000 with 4k7 pullup (E3D)
- * 1010 : Pt1000 with 1k pullup (non standard)
- * 147 : Pt100 with 4k7 pullup
- * 110 : Pt100 with 1k pullup (non standard)
- * 1000 : Custom - Specify parameters in Configuration_adv.h
- * Use these for Testing or Development purposes. NEVER for production machine.
- * 998 : Dummy Table that ALWAYS reads 25°C or the temperature defined below.
- * 999 : Dummy Table that ALWAYS reads 100°C or the temperature defined below.
- */
- #define TEMP_SENSOR_0 61
- #define TEMP_SENSOR_1 0
- #define TEMP_SENSOR_2 0
- #define TEMP_SENSOR_3 0
- #define TEMP_SENSOR_4 0
- #define TEMP_SENSOR_5 0
- #define TEMP_SENSOR_6 0
- #define TEMP_SENSOR_7 0
- #define TEMP_SENSOR_BED 60
- #define TEMP_SENSOR_PROBE 0
- #define TEMP_SENSOR_CHAMBER 0
- #define TEMP_SENSOR_COOLER 0


```

// Dummy thermistor constant temperature readings, for use with 998 and 999
#define DUMMY_THERMISTOR_998_VALUE 25
#define DUMMY_THERMISTOR_999_VALUE 100

// Resistor values when using MAX31865 sensors (-5) on TEMP_SENSOR_0 / 1
// #define MAX31865_SENSOR_OHMS_0 100 // (Ω) Typically 100 or 1000 (PT100 or PT1000)
// #define MAX31865_CALIBRATION_OHMS_0 430 // (Ω) Typically 430 for AdaFruit PT100; 4300
// for AdaFruit PT1000
// #define MAX31865_SENSOR_OHMS_1 100
// #define MAX31865_CALIBRATION_OHMS_1 430

// Use temp sensor 1 as a redundant sensor with sensor 0. If the readings
// from the two sensors differ too much the print will be aborted.
// #define TEMP_SENSOR_1_AS_REDUNDANT
#define MAX_REDUNDANT_TEMP_SENSOR_DIFF 10

#define TEMP_RESIDENCY_TIME 10 // (seconds) Time to wait for hotend to "settle" in M109
#define TEMP_WINDOW 1 // (°C) Temperature proximity for the "temperature reached"
timer
#define TEMP_HYSTERESIS 3 // (°C) Temperature proximity considered "close enough" to
the target

#define TEMP_BED_RESIDENCY_TIME 10 // (seconds) Time to wait for bed to "settle" in M190
#define TEMP_BED_WINDOW 1 // (°C) Temperature proximity for the "temperature
reached" timer
#define TEMP_BED_HYSTERESIS 3 // (°C) Temperature proximity considered "close enough"
to the target

#define TEMP_CHAMBER_RESIDENCY_TIME 10 // (seconds) Time to wait for chamber to
"settle" in M191
#define TEMP_CHAMBER_WINDOW 1 // (°C) Temperature proximity for the "temperature
reached" timer
#define TEMP_CHAMBER_HYSTERESIS 3 // (°C) Temperature proximity considered "close
enough" to the target

// Below this temperature the heater will be switched off
// because it probably indicates a broken thermistor wire.
#define HEATER_0_MINTEMP 5
#define HEATER_1_MINTEMP 5
#define HEATER_2_MINTEMP 5
#define HEATER_3_MINTEMP 5
#define HEATER_4_MINTEMP 5
#define HEATER_5_MINTEMP 5
#define HEATER_6_MINTEMP 5
#define HEATER_7_MINTEMP 5
#define BED_MINTEMP 5
#define CHAMBER_MINTEMP 5

// Above this temperature the heater will be switched off.
// This can protect components from overheating, but NOT from shorts and failures.
// (Use MINTEMP for thermistor short/failure protection.)
#define HEATER_0_MAXTEMP 275
#define HEATER_1_MAXTEMP 275
#define HEATER_2_MAXTEMP 275
#define HEATER_3_MAXTEMP 275
#define HEATER_4_MAXTEMP 275
#define HEATER_5_MAXTEMP 275
#define HEATER_6_MAXTEMP 275
#define HEATER_7_MAXTEMP 275

```

```

#define BED_MAXTEMP 150
#define CHAMBER_MAXTEMP 60

/**
 * Thermal Overshoot
 * During heatup (and printing) the temperature can often "overshoot" the target by many degrees
 * (especially before PID tuning). Setting the target temperature too close to MAXTEMP
guarantees
 * a MAXTEMP shutdown! Use these values to forbid temperatures being set too close to
MAXTEMP.
 */
#define HOTEND_OVERSHOOT 15 // (°C) Forbid temperatures over MAXTEMP - OVERSHOOT
#define BED_OVERSHOOT 10 // (°C) Forbid temperatures over MAXTEMP - OVERSHOOT
#define COOLER_OVERSHOOT 2 // (°C) Forbid temperatures closer than OVERSHOOT

//
=====
==
//===== PID Settings =====
//
=====
==
// PID Tuning Guide here: https://reprap.org/wiki/PID\_Tuning

// Comment the following line to disable PID and enable bang-bang.
#define PIDTEMP
#define BANG_MAX 255 // Limits current to nozzle while in bang-bang mode; 255=full current
#define PID_MAX BANG_MAX // Limits current to nozzle while PID is active (see
PID_FUNCTIONAL_RANGE below); 255=full current
#define PID_K1 0.95 // Smoothing factor within any PID loop

#if ENABLED(PIDTEMP)
  //#define PID_EDIT_MENU // Add PID editing to the "Advanced Settings" menu. (~700
bytes of PROGMEM)
  //#define PID_AUTOTUNE_MENU // Add PID auto-tuning to the "Advanced Settings" menu.
(~250 bytes of PROGMEM)
  //#define PID_PARAMS_PER_HOTEND // Uses separate PID parameters for each extruder
(useful for mismatched extruders)
    // Set/get with gcode: M301 E[extruder number, 0-2]

  #if ENABLED(PID_PARAMS_PER_HOTEND)
    // Specify between 1 and HOTENDS values per array.
    // If fewer than EXTRUDER values are provided, the last element will be repeated.
    #define DEFAULT_Kp_LIST { 22.20, 22.20 }
    #define DEFAULT_Ki_LIST { 1.08, 1.08 }
    #define DEFAULT_Kd_LIST { 114.00, 114.00 }
  #else
    #define DEFAULT_Kp 22.20
    #define DEFAULT_Ki 1.08
    #define DEFAULT_Kd 114.00
  #endif
#endif // PIDTEMP

//
=====
==
//===== PID > Bed Temperature Control =====
//
=====
==

```

```

/**
 * PID Bed Heating
 *
 * If this option is enabled set PID constants below.
 * If this option is disabled, bang-bang will be used and BED_LIMIT_SWITCHING will enable
 hysteresis.
 *
 * The PID frequency will be the same as the extruder PWM.
 * If PID_dT is the default, and correct for the hardware/configuration, that means 7.689Hz,
 * which is fine for driving a square wave into a resistive load and does not significantly
 * impact FET heating. This also works fine on a Fotek SSR-10DA Solid State Relay into a 250W
 * heater. If your configuration is significantly different than this and you don't understand
 * the issues involved, don't use bed PID until someone else verifies that your hardware works.
 */
#define PIDTEMPBED

#define BED_LIMIT_SWITCHING

/**
 * Max Bed Power
 * Applies to all forms of bed control (PID, bang-bang, and bang-bang with hysteresis).
 * When set to any value below 255, enables a form of PWM to the bed that acts like a divider
 * so don't use it unless you are OK with PWM on your bed. (See the comment on enabling
 PIDTEMPBED)
 */
#define MAX_BED_POWER 255 // limits duty cycle to bed; 255=full current

#if ENABLED(PIDTEMPBED)
  #define MIN_BED_POWER 0
  #define PID_BED_DEBUG // Sends debug data to the serial port.

  // 120V 250W silicone heater into 4mm borosilicate (MendelMax 1.5+)
  // from FOPDT model - kp=.39 Tp=405 Tdead=66, Tc set to 79.2, aggressive factor of .15 (vs .1,
  1, 10)
  #define DEFAULT_bedKp 10.00
  #define DEFAULT_bedKi .023
  #define DEFAULT_bedKd 305.4

  // FIND YOUR OWN: "M303 E-1 C8 S90" to run autotune on the bed at 90 degreesC for 8
  cycles.
#endif // PIDTEMPBED

//
=====
==
//===== PID > Chamber Temperature Control =====
//
=====
==

/**
 * PID Chamber Heating
 *
 * If this option is enabled set PID constants below.
 * If this option is disabled, bang-bang will be used and CHAMBER_LIMIT_SWITCHING will
 enable
 * hysteresis.
 *
 * The PID frequency will be the same as the extruder PWM.

```

```

* If PID_dT is the default, and correct for the hardware/configuration, that means 7.689Hz,
* which is fine for driving a square wave into a resistive load and does not significantly
* impact FET heating. This also works fine on a Fetek SSR-10DA Solid State Relay into a 200W
* heater. If your configuration is significantly different than this and you don't understand
* the issues involved, don't use chamber PID until someone else verifies that your hardware
works.
*/
#define PIDTEMPCHAMBER
#define CHAMBER_LIMIT_SWITCHING

/**
 * Max Chamber Power
 * Applies to all forms of chamber control (PID, bang-bang, and bang-bang with hysteresis).
 * When set to any value below 255, enables a form of PWM to the chamber heater that acts like a
divider
 * so don't use it unless you are OK with PWM on your heater. (See the comment on enabling
PIDTEMPCHAMBER)
 */
#define MAX_CHAMBER_POWER 255 // limits duty cycle to chamber heater; 255=full current

#if ENABLED(PIDTEMPCHAMBER)
  #define MIN_CHAMBER_POWER 0
  //#define PID_CHAMBER_DEBUG // Sends debug data to the serial port.

  // Lasko "MyHeat Personal Heater" (200w) modified with a Fetek SSR-10DA to control only the
heating element
  // and placed inside the small Creality printer enclosure tent.
  //
  #define DEFAULT_chamberKp 37.04
  #define DEFAULT_chamberKi 1.40
  #define DEFAULT_chamberKd 655.17
  // M309 P37.04 I1.04 D655.17

  // FIND YOUR OWN: "M303 E-2 C8 S50" to run autotune on the chamber at 50 degreesC for 8
cycles.
#endif // PIDTEMPCHAMBER

#if ANY(PIDTEMP, PIDTEMPBED, PIDTEMPCHAMBER)
  //#define PID_DEBUG // Sends debug data to the serial port. Use 'M303 D' to toggle
activation.
  //#define PID_OPENLOOP // Puts PID in open loop. M104/M140 sets the output power
from 0 to PID_MAX
  //#define SLOW_PWM_HEATERS // PWM with very low frequency (roughly 0.125Hz=8s) and
minimum state time of approximately 1s useful for heaters driven by a relay
  #define PID_FUNCTIONAL_RANGE 10 // If the temperature difference between the target
temperature and the actual temperature
// is more than PID_FUNCTIONAL_RANGE then the PID will be shut off and
the heater will be set to min/max.
#endif

// @section extruder

/**
 * Prevent extrusion if the temperature is below EXTRUDE_MINTEMP.
 * Add M302 to set the minimum extrusion temperature and/or turn
 * cold extrusion prevention on and off.
 *
 * *** IT IS HIGHLY RECOMMENDED TO LEAVE THIS OPTION ENABLED! ***
 */
#define PREVENT_COLD_EXTRUSION

```

```

#define EXTRUDE_MINTEMP 170

/**
 * Prevent a single extrusion longer than EXTRUDE_MAXLENGTH.
 * Note: For Bowden Extruders make this large enough to allow load/unload.
 */
#define PREVENT_LENGTHY_EXTRUDE
#define EXTRUDE_MAXLENGTH 200

//
=====
==
//===== Thermal Runaway Protection =====
//
=====
==

/**
 * Thermal Protection provides additional protection to your printer from damage
 * and fire. Marlin always includes safe min and max temperature ranges which
 * protect against a broken or disconnected thermistor wire.
 *
 * The issue: If a thermistor falls out, it will report the much lower
 * temperature of the air in the room, and the the firmware will keep
 * the heater on.
 *
 * If you get "Thermal Runaway" or "Heating failed" errors the
 * details can be tuned in Configuration_adv.h
 */

#define THERMAL_PROTECTION_HOTENDS // Enable thermal protection for all extruders
#define THERMAL_PROTECTION_BED // Enable thermal protection for the heated bed
#define THERMAL_PROTECTION_CHAMBER // Enable thermal protection for the heated
chamber
#define THERMAL_PROTECTION_COOLER // Enable thermal protection for the laser cooling

//
=====
==
//===== Mechanical Settings =====
//
=====
==

// @section machine

// Enable one of the options below for CoreXY, CoreXZ, or CoreYZ kinematics,
// either in the usual order or reversed
//#define COREXY
//#define COREXZ
//#define COREYZ
#define COREYX
//#define COREZX
//#define COREZY
//#define MARKFORGED_XY // MarkForged. See https://reprap.org/forum/read.php?152,504042

//
=====
==
//===== Endstop Settings =====

```

```

//
=====
==

// @section homing

// Specify here all the endstop connectors that are connected to any endstop or probe.
// Almost all printers will be using one per axis. Probes will use one or more of the
// extra connectors. Leave undefined any used for non-endstop and non-probe purposes.
#define USE_XMIN_PLUG
#define USE_YMIN_PLUG
#define USE_ZMIN_PLUG
//#define USE_XMAX_PLUG
//#define USE_YMAX_PLUG
#define USE_ZMAX_PLUG

// Enable pullup for all endstops to prevent a floating state
#define ENDSTOPPULLUPS
#if DISABLED(ENDSTOPPULLUPS)
  // Disable ENDSTOPPULLUPS to set pullups individually
  //#define ENDSTOPPULLUP_XMAX
  //#define ENDSTOPPULLUP_YMAX
  //#define ENDSTOPPULLUP_ZMAX
  //#define ENDSTOPPULLUP_XMIN
  //#define ENDSTOPPULLUP_YMIN
  //#define ENDSTOPPULLUP_ZMIN
  //#define ENDSTOPPULLUP_ZMIN_PROBE
#endif

// Enable pulldown for all endstops to prevent a floating state
//#define ENDSTOPPULLDOWNS
#if DISABLED(ENDSTOPPULLDOWNS)
  // Disable ENDSTOPPULLDOWNS to set pulldowns individually
  //#define ENDSTOPPULLDOWN_XMAX
  //#define ENDSTOPPULLDOWN_YMAX
  //#define ENDSTOPPULLDOWN_ZMAX
  //#define ENDSTOPPULLDOWN_XMIN
  //#define ENDSTOPPULLDOWN_YMIN
  //#define ENDSTOPPULLDOWN_ZMIN
  //#define ENDSTOPPULLDOWN_ZMIN_PROBE
#endif

// Mechanical endstop with COM to ground and NC to Signal uses "false" here (most common
setup).
#define X_MIN_ENDSTOP_INVERTING true // Set to true to invert the logic of the endstop.
#define Y_MIN_ENDSTOP_INVERTING true // Set to true to invert the logic of the endstop.
#define Z_MIN_ENDSTOP_INVERTING true // Set to true to invert the logic of the endstop.
#define X_MAX_ENDSTOP_INVERTING false // Set to true to invert the logic of the endstop.
#define Y_MAX_ENDSTOP_INVERTING false // Set to true to invert the logic of the endstop.
#define Z_MAX_ENDSTOP_INVERTING true // Set to true to invert the logic of the endstop.
#define Z_MIN_PROBE_ENDSTOP_INVERTING false // Set to true to invert the logic of the probe.

/**
 * Stepper Drivers
 *
 * These settings allow Marlin to tune stepper driver timing and enable advanced options for
 * stepper drivers that support them. You may also override timing options in Configuration_adv.h.
 *
 * A4988 is assumed for unspecified drivers.
 */

```

```

* Use TMC2208/TMC2208_STANDALONE for TMC2225 drivers and TMC2209/
TMC2209_STANDALONE for TMC2226 drivers.
*
* Options: A4988, A5984, DRV8825, LV8729, L6470, L6474, POWERSTEP01,
*         TB6560, TB6600, TMC2100,
*         TMC2130, TMC2130_STANDALONE, TMC2160, TMC2160_STANDALONE,
*         TMC2208, TMC2208_STANDALONE, TMC2209, TMC2209_STANDALONE,
*         TMC26X, TMC26X_STANDALONE, TMC2660, TMC2660_STANDALONE,
*         TMC5130, TMC5130_STANDALONE, TMC5160, TMC5160_STANDALONE
* :['A4988', 'A5984', 'DRV8825', 'LV8729', 'L6470', 'L6474', 'POWERSTEP01', 'TB6560',
'TB6600', 'TMC2100', 'TMC2130', 'TMC2130_STANDALONE', 'TMC2160',
'TMC2160_STANDALONE', 'TMC2208', 'TMC2208_STANDALONE', 'TMC2209',
'TMC2209_STANDALONE', 'TMC26X', 'TMC26X_STANDALONE', 'TMC2660',
'TMC2660_STANDALONE', 'TMC5130', 'TMC5130_STANDALONE', 'TMC5160',
'TMC5160_STANDALONE']
*/
#define X_DRIVER_TYPE TMC2208
#define Y_DRIVER_TYPE TMC2208
#define Z_DRIVER_TYPE TMC2208
//#define X2_DRIVER_TYPE A4988
//#define Y2_DRIVER_TYPE A4988
//#define Z2_DRIVER_TYPE A4988
//#define Z3_DRIVER_TYPE A4988
//#define Z4_DRIVER_TYPE A4988
#define E0_DRIVER_TYPE TMC2208
//#define E1_DRIVER_TYPE A4988
//#define E2_DRIVER_TYPE A4988
//#define E3_DRIVER_TYPE A4988
//#define E4_DRIVER_TYPE A4988
//#define E5_DRIVER_TYPE A4988
//#define E6_DRIVER_TYPE A4988
//#define E7_DRIVER_TYPE A4988

// Enable this feature if all enabled endstop pins are interrupt-capable.
// This will remove the need to poll the interrupt pins, saving many CPU cycles.
//#define ENDSTOP_INTERRUPTS_FEATURE

/**
 * Endstop Noise Threshold
 *
 * Enable if your probe or endstops falsely trigger due to noise.
 *
 * - Higher values may affect repeatability or accuracy of some bed probes.
 * - To fix noise install a 100nF ceramic capacitor in parallel with the switch.
 * - This feature is not required for common micro-switches mounted on PCBs
 *   based on the Makerbot design, which already have the 100nF capacitor.
 *
 * :[2,3,4,5,6,7]
 */
#define ENDSTOP_NOISE_THRESHOLD 2

// Check for stuck or disconnected endstops during homing moves.
#define DETECT_BROKEN_ENDSTOP

//
=====
====
//===== Movement Settings
=====

```

```

//
=====
====
// @section motion

/**
 * Default Settings
 *
 * These settings can be reset by M502
 *
 * Note that if EEPROM is enabled, saved values will override these.
 */

/**
 * With this option each E stepper can have its own factors for the
 * following movement settings. If fewer factors are given than the
 * total number of extruders, the last value applies to the rest.
 */
#define DISTINCT_E_FACTORS

/**
 * Default Axis Steps Per Unit (steps/mm)
 * Override with M92
 *
 * X, Y, Z, E0 [, E1[, E2...]]
 */
#define DEFAULT_AXIS_STEPS_PER_UNIT { 80, 80, 800, 2043.84 }

/**
 * Default Max Feed Rate (mm/s)
 * Override with M203
 *
 * X, Y, Z, E0 [, E1[, E2...]]
 */
#define DEFAULT_MAX_FEEDRATE { 300, 300, 5, 25 }

// #define LIMITED_MAX_FR_EDITING // Limit edit via M203 or LCD to
// DEFAULT_MAX_FEEDRATE * 2
// #if ENABLED(LIMITED_MAX_FR_EDITING)
// #define MAX_FEEDRATE_EDIT_VALUES { 600, 600, 10, 50 } // ...or, set your own edit limits
// #endif

/**
 * Default Max Acceleration (change/s) change = mm/s
 * (Maximum start speed for accelerated moves)
 * Override with M201
 *
 * X, Y, Z, E0 [, E1[, E2...]]
 */
#define DEFAULT_MAX_ACCELERATION { 3000, 3000, 100, 10000 }

// #define LIMITED_MAX_ACCEL_EDITING // Limit edit via M201 or LCD to
// DEFAULT_MAX_ACCELERATION * 2
// #if ENABLED(LIMITED_MAX_ACCEL_EDITING)
// #define MAX_ACCEL_EDIT_VALUES { 6000, 6000, 200, 20000 } // ...or, set your own edit
// limits
// #endif

/**
 * Default Acceleration (change/s) change = mm/s
 * Override with M204
 *
 * M204 P Acceleration

```



```

* M204 R Retract Acceleration
* M204 T Travel Acceleration
*/
#define DEFAULT_ACCELERATION 3000 // X, Y, Z and E acceleration for printing moves
#define DEFAULT_RETRACT_ACCELERATION 3000 // E acceleration for retracts
#define DEFAULT_TRAVEL_ACCELERATION 3000 // X, Y, Z acceleration for travel (non
printing) moves

/**
 * Default Jerk limits (mm/s)
 * Override with M205 X Y Z E
 *
 * "Jerk" specifies the minimum speed change that requires acceleration.
 * When changing speed and direction, if the difference is less than the
 * value set here, it may happen instantaneously.
 */
//#define CLASSIC_JERK
#if ENABLED(CLASSIC_JERK)
#define DEFAULT_XJERK 10.0
#define DEFAULT_YJERK 10.0
#define DEFAULT_ZJERK 0.3

//#define TRAVEL_EXTRA_XYJERK 0.0 // Additional jerk allowance for all travel moves

//#define LIMITED_JERK_EDITING // Limit edit via M205 or LCD to DEFAULT_aJERK * 2
#if ENABLED(LIMITED_JERK_EDITING)
#define MAX_JERK_EDIT_VALUES { 20, 20, 0.6, 10 } // ...or, set your own edit limits
#endif
#endif

#define DEFAULT_EJERK 5.0 // May be used by Linear Advance

/**
 * Junction Deviation Factor
 *
 * See:
 * https://reprap.org/forum/read.php?1,739819
 * https://blog.kyneticcnc.com/2018/10/computing-junction-deviation-for-marlin.html
 */
#if DISABLED(CLASSIC_JERK)
#define JUNCTION_DEVIATION_MM 0.013 // (mm) Distance from real junction edge
#define JD_HANDLE_SMALL_SEGMENTS // Use curvature estimation instead of just the
junction angle
// for small segments (< 1mm) with large junction angles (> 135°).
#endif

/**
 * S-Curve Acceleration
 *
 * This option eliminates vibration during printing by fitting a Bézier
 * curve to move acceleration, producing much smoother direction changes.
 *
 * See https://github.com/synthetos/TinyG/wiki/Jerk-Controlled-Motion-Explained
 */
//#define S_CURVE_ACCELERATION

//
=====
==
//===== Z Probe Options =====

```

```

//
=====
==
// @section probes

//
// See https://marlinfw.org/docs/configuration/probes.html
//

/**
 * Enable this option for a probe connected to the Z-MIN pin.
 * The probe replaces the Z-MIN endstop and is used for Z homing.
 * (Automatically enables USE_PROBE_FOR_Z_HOMING.)
 */
#define Z_MIN_PROBE_USES_Z_MIN_ENDSTOP_PIN

// Force the use of the probe for Z-axis homing
#define USE_PROBE_FOR_Z_HOMING

/**
 * Z_MIN_PROBE_PIN
 *
 * Define this pin if the probe is not connected to Z_MIN_PIN.
 * If not defined the default pin for the selected MOTHERBOARD
 * will be used. Most of the time the default is what you want.
 *
 * - The simplest option is to use a free endstop connector.
 * - Use 5V for powered (usually inductive) sensors.
 *
 * - RAMPS 1.3/1.4 boards may use the 5V, GND, and Aux4->D32 pin:
 *   - For simple switches connect...
 *     - normally-closed switches to GND and D32.
 *     - normally-open switches to 5V and D32.
 */
#define Z_MIN_PROBE_PIN 32 // Pin 32 is the RAMPS default

/**
 * Probe Type
 *
 * Allen Key Probes, Servo Probes, Z-Sled Probes, FIX_MOUNTED_PROBE, etc.
 * Activate one of these to use Auto Bed Leveling below.
 */

/**
 * The "Manual Probe" provides a means to do "Auto" Bed Leveling without a probe.
 * Use G29 repeatedly, adjusting the Z height at each point with movement commands
 * or (with LCD_BED_LEVELING) the LCD controller.
 */
#define PROBE_MANUALLY
#define MANUAL_PROBE_START_Z 0.2

/**
 * A Fix-Mounted Probe either doesn't deploy or needs manual deployment.
 * (e.g., an inductive probe or a nozzle-based probe-switch.)
 */
#define FIX_MOUNTED_PROBE

/**
 * Use the nozzle as the probe, as with a conductive
 * nozzle system or a piezo-electric smart effector.

```

```

*/

//#define NOZZLE_AS_PROBE

/**
 * Z Servo Probe, such as an endstop switch on a rotating arm.
 */

//#define Z_PROBE_SERVO_NR 0 // Defaults to SERVO 0 connector.
//#define Z_SERVO_ANGLES { 70, 0 } // Z Servo Deploy and Stow angles

/**
 * The BLTouch probe uses a Hall effect sensor and emulates a servo.
 */

//#define BLTOUCH

/**
 * Touch-MI Probe by hotends.fr
 *
 * This probe is deployed and activated by moving the X-axis to a magnet at the edge of the bed.
 * By default, the magnet is assumed to be on the left and activated by a home. If the magnet is
 * on the right, enable and set TOUCH_MI_DEPLOY_XPOS to the deploy position.
 *
 * Also requires: BABYSTEPPING, BABYSTEP_ZPROBE_OFFSET, Z_SAFE_HOMING,
 * and a minimum Z_HOMING_HEIGHT of 10.
 */

//#define TOUCH_MI_PROBE
#if ENABLED(TOUCH_MI_PROBE)
  #define TOUCH_MI_RETRACT_Z 0.5 // Height at which the probe retracts
  // #define TOUCH_MI_DEPLOY_XPOS (X_MAX_BED + 2) // For a magnet on the right side of the
  bed
  // #define TOUCH_MI_MANUAL_DEPLOY // For manual deploy (LCD menu)
#endif

// A probe that is deployed and stowed with a solenoid pin (SOL1_PIN)
// #define SOLENOID_PROBE

// A sled-mounted probe like those designed by Charles Bell.
// #define Z_PROBE_SLED
// #define SLED_DOCKING_OFFSET 5 // The extra distance the X axis must travel to pickup the
sled. 0 should be fine but you can push it further if you'd like.

// A probe deployed by moving the x-axis, such as the Wilson II's rack-and-pinion probe designed
by Marty Rice.
// #define RACK_AND_PINION_PROBE
#if ENABLED(RACK_AND_PINION_PROBE)
  #define Z_PROBE_DEPLOY_X X_MIN_POS
  #define Z_PROBE_RETRACT_X X_MAX_POS
#endif

// Duet Smart Effector (for delta printers) - https://bit.ly/2u15U7J
// When the pin is defined you can use M672 to set/reset the probe sensitivity.
// #define DUET_SMART_EFFECTOR
#if ENABLED(DUET_SMART_EFFECTOR)
  #define SMART_EFFECTOR_MOD_PIN -1 // Connect a GPIO pin to the Smart Effector MOD
  pin
#endif

/**
 * Use StallGuard2 to probe the bed with the nozzle.
 * Requires stallGuard-capable Trinamic stepper drivers.
 * CAUTION: This can damage machines with Z lead screws.


```

```

*      Take extreme care when setting up this feature.
*/
##define SENSORLESS_PROBING

//
// For Z_PROBE_ALLEN_KEY see the Delta example configurations.
//

/**
* Nozzle-to-Probe offsets { X, Y, Z }
*
* X and Y offset
* Use a caliper or ruler to measure the distance from the tip of
* the Nozzle to the center-point of the Probe in the X and Y axes.
*
* Z offset
* - For the Z offset use your best known value and adjust at runtime.
* - Common probes trigger below the nozzle and have negative values for Z offset.
* - Probes triggering above the nozzle height are uncommon but do exist. When using
* probes such as this, carefully set Z_CLEARANCE_DEPLOY_PROBE and
Z_CLEARANCE_BETWEEN_PROBES
* to avoid collisions during probing.
*
* Tune and Adjust
* - Probe Offsets can be tuned at runtime with 'M851', LCD menus, babystepping, etc.
* - PROBE_OFFSET_WIZARD (configuration_adv.h) can be used for setting the Z offset.
*
* Assuming the typical work area orientation:
* - Probe to RIGHT of the Nozzle has a Positive X offset
* - Probe to LEFT of the Nozzle has a Negative X offset
* - Probe in BACK of the Nozzle has a Positive Y offset
* - Probe in FRONT of the Nozzle has a Negative Y offset
*
* Some examples:
* #define NOZZLE_TO_PROBE_OFFSET { 10, 10, -1 } // Example "1"
* #define NOZZLE_TO_PROBE_OFFSET { -10, 5, -1 } // Example "2"
* #define NOZZLE_TO_PROBE_OFFSET { 5, -5, -1 } // Example "3"
* #define NOZZLE_TO_PROBE_OFFSET { -15,-10, -1 } // Example "4"
*
* +-- BACK ---+
* |  [+]  |
* L |    1 | R <-- Example "1" (right+, back+)
* E |  2   | I <-- Example "2" (left-, back+)
* F | [-] N [+] | G <-- Nozzle
* T |    3 | H <-- Example "3" (right+, front-)
* |  4   | T <-- Example "4" (left-, front-)
* |  [-]  |
* O-- FRONT ---+
*/
##define NOZZLE_TO_PROBE_OFFSET { 10, 10, 0 }

// Most probes should stay away from the edges of the bed, but
// with NOZZLE_AS_PROBE this can be negative for a wider probing area.
##define PROBING_MARGIN 10

// X and Y axis travel speed (mm/min) between probes
##define XY_PROBE_FEEDRATE (133*60)

// Feedrate (mm/min) for the first approach when double-probing (MULTIPLE_PROBING == 2)
##define Z_PROBE_FEEDRATE_FAST (4*60)

```

```

// Feedrate (mm/min) for the "accurate" probe of each point
//#define Z_PROBE_FEEDRATE_SLOW (Z_PROBE_FEEDRATE_FAST / 2)

/**
 * Probe Activation Switch
 * A switch indicating proper deployment, or an optical
 * switch triggered when the carriage is near the bed.
 */
//#define PROBE_ACTIVATION_SWITCH
#if ENABLED(PROBE_ACTIVATION_SWITCH)
  #define PROBE_ACTIVATION_SWITCH_STATE LOW // State indicating probe is active
  //#define PROBE_ACTIVATION_SWITCH_PIN PC6 // Override default pin
#endif

/**
 * Tare Probe (determine zero-point) prior to each probe.
 * Useful for a strain gauge or piezo sensor that needs to factor out
 * elements such as cables pulling on the carriage.
 */
//#define PROBE_TARE
#if ENABLED(PROBE_TARE)
  #define PROBE_TARE_TIME 200 // (ms) Time to hold tare pin
  #define PROBE_TARE_DELAY 200 // (ms) Delay after tare before
  #define PROBE_TARE_STATE HIGH // State to write pin for tare
  //#define PROBE_TARE_PIN PA5 // Override default pin
  #if ENABLED(PROBE_ACTIVATION_SWITCH)
    //#define PROBE_TARE_ONLY_WHILE_INACTIVE // Fail to tare/probe if
    PROBE_ACTIVATION_SWITCH is active
  #endif
#endif

/**
 * Multiple Probing
 *
 * You may get improved results by probing 2 or more times.
 * With EXTRA_PROBING the more atypical reading(s) will be disregarded.
 *
 * A total of 2 does fast/slow probes with a weighted average.
 * A total of 3 or more adds more slow probes, taking the average.
 */
//#define MULTIPLE_PROBING 2
//#define EXTRA_PROBING 1

/**
 * Z probes require clearance when deploying, stowing, and moving between
 * probe points to avoid hitting the bed and other hardware.
 * Servo-mounted probes require extra space for the arm to rotate.
 * Inductive probes need space to keep from triggering early.
 *
 * Use these settings to specify the distance (mm) to raise the probe (or
 * lower the bed). The values set here apply over and above any (negative)
 * probe Z Offset set with NOZZLE_TO_PROBE_OFFSET, M851, or the LCD.
 * Only integer values >= 1 are valid here.
 *
 * Example: `M851 Z-5` with a CLEARANCE of 4 => 9mm from bed to nozzle.
 * But: `M851 Z+1` with a CLEARANCE of 2 => 2mm from bed to nozzle.
 */
//#define Z_CLEARANCE_DEPLOY_PROBE 10 // Z Clearance for Deploy/Stow
//#define Z_CLEARANCE_BETWEEN_PROBES 5 // Z Clearance between probe points

```

```

//#define Z_CLEARANCE_MULTI_PROBE 5 // Z Clearance between multiple probes
//#define Z_AFTER_PROBING 5 // Z position after probing is done

//#define Z_PROBE_LOW_POINT -2 // Farthest distance below the trigger-point to go before
stopping

// For M851 give a range for adjusting the Z probe offset
//#define Z_PROBE_OFFSET_RANGE_MIN -20
//#define Z_PROBE_OFFSET_RANGE_MAX 20

// Enable the M48 repeatability test to test probe accuracy
//#define Z_MIN_PROBE_REPEATABILITY_TEST

// Before deploy/stow pause for user confirmation
//#define PAUSE_BEFORE_DEPLOY_STOW
#if ENABLED(PAUSE_BEFORE_DEPLOY_STOW)
  //#define PAUSE_PROBE_DEPLOY_WHEN_TRIGGERED // For Manual Deploy Allenkey Probe
#endif

/**
 * Enable one or more of the following if probing seems unreliable.
 * Heaters and/or fans can be disabled during probing to minimize electrical
 * noise. A delay can also be added to allow noise and vibration to settle.
 * These options are most useful for the BLTouch probe, but may also improve
 * readings with inductive probes and piezo sensors.
 */
//#define PROBING_HEATERS_OFF // Turn heaters off when probing
#if ENABLED(PROBING_HEATERS_OFF)
  //#define WAIT_FOR_BED_HEATER // Wait for bed to heat back up between probes (to
improve accuracy)
  //#define WAIT_FOR_HOTEND // Wait for hotend to heat back up between probes (to
improve accuracy & prevent cold extrude)
#endif
//#define PROBING_FANS_OFF // Turn fans off when probing
//#define PROBING_STEPPERS_OFF // Turn steppers off (unless needed to hold position)
when probing
//#define DELAY_BEFORE_PROBING 200 // (ms) To prevent vibrations from triggering piezo
sensors

// Require minimum nozzle and/or bed temperature for probing
//#define PREHEAT_BEFORE_PROBING
#if ENABLED(PREHEAT_BEFORE_PROBING)
  #define PROBING_NOZZLE_TEMP 120 // (°C) Only applies to E0 at this time
  #define PROBING_BED_TEMP 50
#endif

// For Inverting Stepper Enable Pins (Active Low) use 0, Non Inverting (Active High) use 1
// :{ 0:'Low', 1:'High' }
#define X_ENABLE_ON 0
#define Y_ENABLE_ON 0
#define Z_ENABLE_ON 0
#define E_ENABLE_ON 0 // For all extruders

// Disable axis steppers immediately when they're not being stepped.
// WARNING: When motors turn off there is a chance of losing position accuracy!
#define DISABLE_X false
#define DISABLE_Y false
#define DISABLE_Z false

// Turn off the display blinking that warns about possible accuracy reduction

```

```

//#define DISABLE_REDUCED_ACCURACY_WARNING

// @section extruder

#define DISABLE_E false // Disable the extruder when not stepping
#define DISABLE_INACTIVE_EXTRUDER // Keep only the active extruder enabled

// @section machine

// Invert the stepper direction. Change (or reverse the motor connector) if an axis goes the wrong
way.
#define INVERT_X_DIR true
#define INVERT_Y_DIR false
#define INVERT_Z_DIR true

// @section extruder

// For direct drive extruder v9 set to true, for geared extruder set to false.
#define INVERT_E0_DIR true
#define INVERT_E1_DIR false
#define INVERT_E2_DIR false
#define INVERT_E3_DIR false
#define INVERT_E4_DIR false
#define INVERT_E5_DIR false
#define INVERT_E6_DIR false
#define INVERT_E7_DIR false

// @section homing

//#define NO_MOTION_BEFORE_HOMING // Inhibit movement until all axes have been homed.
Also enable HOME_AFTER_DEACTIVATE for extra safety.
//#define HOME_AFTER_DEACTIVATE // Require rehoming after steppers are deactivated. Also
enable NO_MOTION_BEFORE_HOMING for extra safety.

/**
 * Set Z_IDLE_HEIGHT if the Z-Axis moves on its own when steppers are disabled.
 * - Use a low value (i.e., Z_MIN_POS) if the nozzle falls down to the bed.
 * - Use a large value (i.e., Z_MAX_POS) if the bed falls down, away from the nozzle.
 */
//#define Z_IDLE_HEIGHT Z_HOME_POS

//#define Z_HOMING_HEIGHT 4 // (mm) Minimal Z height before homing (G28) for Z clearance
above the bed, clamps, ...
// Be sure to have this much clearance over your Z_MAX_POS to prevent
grinding.

//#define Z_AFTER_HOMING 10 // (mm) Height to move to after homing Z

// Direction of endstops when homing; 1=MAX, -1=MIN
// :[-1,1]
#define X_HOME_DIR -1
#define Y_HOME_DIR -1
#define Z_HOME_DIR -1

// @section machine

// The size of the print bed
#define X_BED_SIZE 400
#define Y_BED_SIZE 400

```

```

// Travel limits (mm) after homing, corresponding to endstop positions.
#define X_MIN_POS 0
#define Y_MIN_POS 0
#define Z_MIN_POS 0
#define X_MAX_POS X_BED_SIZE
#define Y_MAX_POS Y_BED_SIZE
#define Z_MAX_POS 350

/**
 * Software Endstops
 *
 * - Prevent moves outside the set machine bounds.
 * - Individual axes can be disabled, if desired.
 * - X and Y only apply to Cartesian robots.
 * - Use 'M211' to set software endstops on/off or report current state
 */

// Min software endstops constrain movement within minimum coordinate bounds
#define MIN_SOFTWARE_ENDSTOPS
#if ENABLED(MIN_SOFTWARE_ENDSTOPS)
  #define MIN_SOFTWARE_ENDSTOP_X
  #define MIN_SOFTWARE_ENDSTOP_Y
  #define MIN_SOFTWARE_ENDSTOP_Z
#endif

// Max software endstops constrain movement within maximum coordinate bounds
#define MAX_SOFTWARE_ENDSTOPS
#if ENABLED(MAX_SOFTWARE_ENDSTOPS)
  #define MAX_SOFTWARE_ENDSTOP_X
  #define MAX_SOFTWARE_ENDSTOP_Y
  #define MAX_SOFTWARE_ENDSTOP_Z
#endif

#if EITHER(MIN_SOFTWARE_ENDSTOPS, MAX_SOFTWARE_ENDSTOPS)
  //#define SOFT_ENDSTOPS_MENU_ITEM // Enable/Disable software endstops from the LCD
#endif

/**
 * Filament Runout Sensors
 * Mechanical or opto endstops are used to check for the presence of filament.
 *
 * IMPORTANT: Runout will only trigger if Marlin is aware that a print job is running.
 * Marlin knows a print job is running when:
 * 1. Running a print job from media started with M24.
 * 2. The Print Job Timer has been started with M75.
 * 3. The heaters were turned on and PRINTJOB_TIMER_AUTOSTART is enabled.
 *
 * RAMPS-based boards use SERVO3_PIN for the first runout sensor.
 * For other boards you may need to define FIL_RUNOUT_PIN, FIL_RUNOUT2_PIN, etc.
 */
//#define FILAMENT_RUNOUT_SENSOR
#if ENABLED(FILAMENT_RUNOUT_SENSOR)
  #define FIL_RUNOUT_ENABLED_DEFAULT true // Enable the sensor on startup. Override with
M412 followed by M500.
  #define NUM_RUNOUT_SENSORS 1 // Number of sensors, up to one per extruder.
  Define a FIL_RUNOUT#_PIN for each.

  #define FIL_RUNOUT_STATE LOW // Pin state indicating that filament is NOT present.
  #define FIL_RUNOUT_PULLUP // Use internal pullup for filament runout pins.
  //#define FIL_RUNOUT_PULLDOWN // Use internal pulldown for filament runout pins.

```



```
//#define WATCH_ALL_RUNOUT_SENSORS // Execute runout script on any triggering
sensor, not only for the active extruder.
```

```
    // This is automatically enabled for MIXING_EXTRUDERS.
```

```
// Override individually if the runout sensors vary
```

```
//#define FIL_RUNOUT1_STATE LOW
```

```
//#define FIL_RUNOUT1_PULLUP
```

```
//#define FIL_RUNOUT1_PULLDOWN
```

```
//#define FIL_RUNOUT2_STATE LOW
```

```
//#define FIL_RUNOUT2_PULLUP
```

```
//#define FIL_RUNOUT2_PULLDOWN
```

```
//#define FIL_RUNOUT3_STATE LOW
```

```
//#define FIL_RUNOUT3_PULLUP
```

```
//#define FIL_RUNOUT3_PULLDOWN
```

```
//#define FIL_RUNOUT4_STATE LOW
```

```
//#define FIL_RUNOUT4_PULLUP
```

```
//#define FIL_RUNOUT4_PULLDOWN
```

```
//#define FIL_RUNOUT5_STATE LOW
```

```
//#define FIL_RUNOUT5_PULLUP
```

```
//#define FIL_RUNOUT5_PULLDOWN
```

```
//#define FIL_RUNOUT6_STATE LOW
```

```
//#define FIL_RUNOUT6_PULLUP
```

```
//#define FIL_RUNOUT6_PULLDOWN
```

```
//#define FIL_RUNOUT7_STATE LOW
```

```
//#define FIL_RUNOUT7_PULLUP
```

```
//#define FIL_RUNOUT7_PULLDOWN
```

```
//#define FIL_RUNOUT8_STATE LOW
```

```
//#define FIL_RUNOUT8_PULLUP
```

```
//#define FIL_RUNOUT8_PULLDOWN
```

```
// Commands to execute on filament runout.
```

```
// With multiple runout sensors use the %c placeholder for the current tool in commands (e.g.,
"M600 T%c")
```

```
// NOTE: After 'M412 H1' the host handles filament runout and this script does not apply.
```

```
#define FILAMENT_RUNOUT_SCRIPT "M600"
```

```
// After a runout is detected, continue printing this length of filament
```

```
// before executing the runout script. Useful for a sensor at the end of
```

```
// a feed tube. Requires 4 bytes SRAM per sensor, plus 4 bytes overhead.
```

```
//#define FILAMENT_RUNOUT_DISTANCE_MM 25
```

```
#ifdef FILAMENT_RUNOUT_DISTANCE_MM
```

```
    // Enable this option to use an encoder disc that toggles the runout pin
```

```
    // as the filament moves. (Be sure to set FILAMENT_RUNOUT_DISTANCE_MM
```

```
    // large enough to avoid false positives.)
```

```
    //#define FILAMENT_MOTION_SENSOR
```

```
#endif
```

```
#endif
```

```
//
```

```
=====
```

```
==
```

```
//===== Bed Leveling =====
```

```

//
=====
==
// @section calibrate

/**
 * Choose one of the options below to enable G29 Bed Leveling. The parameters
 * and behavior of G29 will change depending on your selection.
 *
 * If using a Probe for Z Homing, enable Z_SAFE_HOMING also!
 *
 * - AUTO_BED_LEVELING_3POINT
 * Probe 3 arbitrary points on the bed (that aren't collinear)
 * You specify the XY coordinates of all 3 points.
 * The result is a single tilted plane. Best for a flat bed.
 *
 * - AUTO_BED_LEVELING_LINEAR
 * Probe several points in a grid.
 * You specify the rectangle and the density of sample points.
 * The result is a single tilted plane. Best for a flat bed.
 *
 * - AUTO_BED_LEVELING_BILINEAR
 * Probe several points in a grid.
 * You specify the rectangle and the density of sample points.
 * The result is a mesh, best for large or uneven beds.
 *
 * - AUTO_BED_LEVELING_UBL (Unified Bed Leveling)
 * A comprehensive bed leveling system combining the features and benefits
 * of other systems. UBL also includes integrated Mesh Generation, Mesh
 * Validation and Mesh Editing systems.
 *
 * - MESH_BED_LEVELING
 * Probe a grid manually
 * The result is a mesh, suitable for large or uneven beds. (See BILINEAR.)
 * For machines without a probe, Mesh Bed Leveling provides a method to perform
 * leveling in steps so you can manually adjust the Z height at each grid-point.
 * With an LCD controller the process is guided step-by-step.
 */
#define AUTO_BED_LEVELING_3POINT
#define AUTO_BED_LEVELING_LINEAR
#define AUTO_BED_LEVELING_BILINEAR
#define AUTO_BED_LEVELING_UBL
#define MESH_BED_LEVELING

/**
 * Normally G28 leaves leveling disabled on completion. Enable one of
 * these options to restore the prior leveling state or to always enable
 * leveling immediately after G28.
 */
#define RESTORE_LEVELING_AFTER_G28
#define ENABLE_LEVELING_AFTER_G28

/**
 * Auto-leveling needs preheating
 */
#define PREHEAT_BEFORE_LEVELING
#if ENABLED(PREHEAT_BEFORE_LEVELING)
  #define LEVELING_NOZZLE_TEMP 120 // (°C) Only applies to E0 at this time
  #define LEVELING_BED_TEMP 50
#endif

```

```

/**
 * Enable detailed logging of G28, G29, M48, etc.
 * Turn on with the command 'M111 S32'.
 * NOTE: Requires a lot of PROGMEM!
 */
//#define DEBUG_LEVELING_FEATURE

#if ANY(MESH_BED_LEVELING, AUTO_BED_LEVELING_BILINEAR, AUTO_BED_LEVELING_UBL)
  // Gradually reduce leveling correction until a set height is reached,
  // at which point movement will be level to the machine's XY plane.
  // The height can be set with M420 Z<height>
  #define ENABLE_LEVELING_FADE_HEIGHT
  #if ENABLED(ENABLE_LEVELING_FADE_HEIGHT)
    #define DEFAULT_LEVELING_FADE_HEIGHT 10.0 // (mm) Default fade height.
  #endif

  // For Cartesian machines, instead of dividing moves on mesh boundaries,
  // split up moves into short segments like a Delta. This follows the
  // contours of the bed more closely than edge-to-edge straight moves.
  #define SEGMENT_LEVELLED_MOVES
  #define LEVELLED_SEGMENT_LENGTH 5.0 // (mm) Length of all segments (except the last one)

/**
 * Enable the G26 Mesh Validation Pattern tool.
 */
//#define G26_MESH_VALIDATION
#if ENABLED(G26_MESH_VALIDATION)
  #define MESH_TEST_NOZZLE_SIZE 0.4 // (mm) Diameter of primary nozzle.
  #define MESH_TEST_LAYER_HEIGHT 0.2 // (mm) Default layer height for G26.
  #define MESH_TEST_HOTEND_TEMP 205 // (°C) Default nozzle temperature for G26.
  #define MESH_TEST_BED_TEMP 60 // (°C) Default bed temperature for G26.
  #define G26_XY_FEEDRATE 20 // (mm/s) Feedrate for G26 XY moves.
  #define G26_XY_FEEDRATE_TRAVEL 100 // (mm/s) Feedrate for G26 XY travel moves.
  #define G26_RETRACT_MULTIPLIER 1.0 // G26 Q (retraction) used by default between mesh
test elements.
  #endif

#endif

#if EITHER(AUTO_BED_LEVELING_LINEAR, AUTO_BED_LEVELING_BILINEAR)

  // Set the number of grid points per dimension.
  #define GRID_MAX_POINTS_X 3
  #define GRID_MAX_POINTS_Y GRID_MAX_POINTS_X

  // Probe along the Y axis, advancing X after each column
  //#define PROBE_Y_FIRST

  #if ENABLED(AUTO_BED_LEVELING_BILINEAR)

    // Beyond the probed grid, continue the implied tilt?
    // Default is to maintain the height of the nearest edge.
    //#define EXTRAPOLATE_BEYOND_GRID

    //
    // Experimental Subdivision of the grid by Catmull-Rom method.
    // Synthesizes intermediate points to produce a more detailed mesh.
    //
    //#define ABL_BILINEAR_SUBDIVISION

```

```

    #if ENABLED(ABL_BILINEAR_SUBDIVISION)
      // Number of subdivisions between probe points
      #define BILINEAR_SUBDIVISIONS 3
    #endif

  #endif

  #elif ENABLED(AUTO_BED_LEVELING_UBL)

    //
    =====
    ==
    //===== Unified Bed Leveling =====
    //
    =====
    ==

    //#define MESH_EDIT_GFX_OVERLAY // Display a graphics overlay while editing the mesh

    #define MESH_INSET 1 // Set Mesh bounds as an inset region of the bed
    #define GRID_MAX_POINTS_X 10 // Don't use more than 15 points per axis, implementation
    limited.
    #define GRID_MAX_POINTS_Y GRID_MAX_POINTS_X

    //#define UBL_HILBERT_CURVE // Use Hilbert distribution for less travel when probing
    multiple points

    #define UBL_MESH_EDIT_MOVES_Z // Sophisticated users prefer no movement of nozzle
    #define UBL_SAVE_ACTIVE_ON_M500 // Save the currently active mesh in the current slot on
    M500

    //#define UBL_Z_RAISE_WHEN_OFF_MESH 2.5 // When the nozzle is off the mesh, this value is
    used
    // as the Z-Height correction value.

  #elif ENABLED(MESH_BED_LEVELING)

    //
    =====
    ==
    //===== Mesh =====
    //
    =====
    ==

    #define MESH_INSET 10 // Set Mesh bounds as an inset region of the bed
    #define GRID_MAX_POINTS_X 3 // Don't use more than 7 points per axis, implementation
    limited.
    #define GRID_MAX_POINTS_Y GRID_MAX_POINTS_X

    //#define MESH_G28_REST_ORIGIN // After homing all axes ('G28' or 'G28 XYZ') rest Z at
    Z_MIN_POS

  #endif // BED_LEVELING

/**
 * Add a bed leveling sub-menu for ABL or MBL.
 * Include a guided procedure if manual probing is enabled.
 */

```

```

##define LCD_BED_LEVELING

#if ENABLED(LCD_BED_LEVELING)
  #define MESH_EDIT_Z_STEP 0.025 // (mm) Step size while manually probing Z axis.
  #define LCD_PROBE_Z_RANGE 4 // (mm) Z Range centered on Z_MIN_POS for LCD Z
  adjustment
  ##define MESH_EDIT_MENU // Add a menu to edit mesh points
#endif

// Add a menu item to move between bed corners for manual bed adjustment
##define LEVEL_BED_CORNERS

#if ENABLED(LEVEL_BED_CORNERS)
  #define LEVEL_CORNERS_INSET_LFRB { 30, 30, 30, 30 } // (mm) Left, Front, Right, Back insets
  #define LEVEL_CORNERS_HEIGHT 0.0 // (mm) Z height of nozzle at leveling points
  #define LEVEL_CORNERS_Z_HOP 4.0 // (mm) Z height of nozzle between leveling points
  ##define LEVEL_CENTER_TOO // Move to the center after the last corner
  ##define LEVEL_CORNERS_USE_PROBE
  #if ENABLED(LEVEL_CORNERS_USE_PROBE)
    #define LEVEL_CORNERS_PROBE_TOLERANCE 0.1
    #define LEVEL_CORNERS_VERIFY_RAISED // After adjustment triggers the probe, re-probe
  to verify
    ##define LEVEL_CORNERS_AUDIO_FEEDBACK
  #endif

/**
 * Corner Leveling Order
 *
 * Set 2 or 4 points. When 2 points are given, the 3rd is the center of the opposite edge.
 *
 * LF Left-Front RF Right-Front
 * LB Left-Back RB Right-Back
 *
 * Examples:
 *
 * Default {LF, RB, LB, RF} {LF, RF} {LB, LB}
 * LB ----- RB LB ----- RB LB ----- RB LB ----- RB
 * | 4 3 | | 3 2 | | <3> | | 1 |
 * | | | | | | | | | | | |
 * | 1 2 | | 1 4 | | 1 2 | | 2 |
 * LF ----- RF LF ----- RF LF ----- RF LF ----- RF
 */
  #define LEVEL_CORNERS_LEVELING_ORDER { LF, RF, RB, LB }
#endif

/**
 * Commands to execute at the end of G29 probing.
 * Useful to retract or move the Z probe out of the way.
 */
##define Z_PROBE_END_SCRIPT "G1 Z10 F12000\nG1 X15 Y330\nG1 Z0.5\nG1 Z10"

// @section homing

// The center of the bed is at (X=0, Y=0)
##define BED_CENTER_AT_0_0

// Manually set the home position. Leave these undefined for automatic settings.
// For DELTA this is the top-center of the Cartesian print volume.
##define MANUAL_X_HOME_POS 0
##define MANUAL_Y_HOME_POS 0

```

```

// #define MANUAL_Z_HOME_POS 0

// Use "Z Safe Homing" to avoid homing with a Z probe outside the bed area.
//
// With this feature enabled:
//
// - Allow Z homing only after X and Y homing AND stepper drivers still enabled.
// - If stepper drivers time out, it will need X and Y homing again before Z homing.
// - Move the Z probe (or nozzle) to a defined XY point before Z Homing.
// - Prevent Z homing when the Z probe is outside bed area.
//
// #define Z_SAFE_HOMING

#if ENABLED(Z_SAFE_HOMING)
  #define Z_SAFE_HOMING_X_POINT X_CENTER // X point for Z homing
  #define Z_SAFE_HOMING_Y_POINT Y_CENTER // Y point for Z homing
#endif

// Homing speeds (mm/min)
#define HOMING_FEEDRATE_MM_M { (50*60), (50*60), (4*60) }

// Validate that endstops are triggered on homing moves
#define VALIDATE_HOMING_ENDSTOPS

// @section calibrate

/**
 * Bed Skew Compensation
 *
 * This feature corrects for misalignment in the XYZ axes.
 *
 * Take the following steps to get the bed skew in the XY plane:
 * 1. Print a test square (e.g., https://www.thingiverse.com/thing:2563185)
 * 2. For XY_DIAG_AC measure the diagonal A to C
 * 3. For XY_DIAG_BD measure the diagonal B to D
 * 4. For XY_SIDE_AD measure the edge A to D
 *
 * Marlin automatically computes skew factors from these measurements.
 * Skew factors may also be computed and set manually:
 *
 * - Compute AB : SQRT(2*AC*AC+2*BD*BD-4*AD*AD)/2
 * - XY_SKEW_FACTOR : TAN(PI/2-ACOS((AC*AC-AB*AB-AD*AD)/(2*AB*AD)))
 *
 * If desired, follow the same procedure for XZ and YZ.
 * Use these diagrams for reference:
 *
 *
 * Y           Z           Z
 * ^           ^           ^
 * B-----C   B-----C   B-----C
 * | / / /     | / / /     | / / /
 * | / / /     | / / /     | / / /
 * | A-----D   | A-----D   | A-----D
 * +----->X   +----->X   +----->Y
 * XY_SKEW_FACTOR   XZ_SKEW_FACTOR   YZ_SKEW_FACTOR
 */
// #define SKEW_CORRECTION

#if ENABLED(SKEW_CORRECTION)
  // Input all length measurements here:
  #define XY_DIAG_AC 282.8427124746
  #define XY_DIAG_BD 282.8427124746

```

```

#define XY_SIDE_AD 200

// Or, set the default skew factors directly here
// to override the above measurements:
#define XY_SKEW_FACTOR 0.0

//#define SKEW_CORRECTION_FOR_Z
#if ENABLED(SKEW_CORRECTION_FOR_Z)
  #define XZ_DIAG_AC 282.8427124746
  #define XZ_DIAG_BD 282.8427124746
  #define YZ_DIAG_AC 282.8427124746
  #define YZ_DIAG_BD 282.8427124746
  #define YZ_SIDE_AD 200
  #define XZ_SKEW_FACTOR 0.0
  #define YZ_SKEW_FACTOR 0.0
#endif

// Enable this option for M852 to set skew at runtime
//#define SKEW_CORRECTION_GCODE
#endif

//
=====
====
//===== Additional Features =====
//
=====
====

// @section extras

/**
 * EEPROM
 *
 * Persistent storage to preserve configurable settings across reboots.
 *
 * M500 - Store settings to EEPROM.
 * M501 - Read settings from EEPROM. (i.e., Throw away unsaved changes)
 * M502 - Revert settings to "factory" defaults. (Follow with M500 to init the EEPROM.)
 */
#define EEPROM_SETTINGS // Persistent storage with M500 and M501
//#define DISABLE_M503 // Saves ~2700 bytes of PROGMEM. Disable for release!
#define EEPROM_CHITCHAT // Give feedback on EEPROM commands. Disable to save PROGMEM.
#define EEPROM_BOOT_SILENT // Keep M503 quiet and only give errors during first load
#if ENABLED(EEPROM_SETTINGS)
  //#define EEPROM_AUTO_INIT // Init EEPROM automatically on any errors.
#endif

//
// Host Keepalive
//
// When enabled Marlin will send a busy status message to the host
// every couple of seconds when it can't accept commands.
//
#define HOST_KEEPALIVE_FEATURE // Disable this if your host doesn't like keepalive
messages
#define DEFAULT_KEEPALIVE_INTERVAL 2 // Number of seconds between "busy" messages.
Set with M113.

```

```

#define BUSY_WHILE_HEATING          // Some hosts require "busy" messages even during
heating

//
// G20/G21 Inch mode support
//
//#define INCH_MODE_SUPPORT

//
// M149 Set temperature units support
//
//#define TEMPERATURE_UNITS_SUPPORT

// @section temperature

//
// Preheat Constants - Up to 5 are supported without changes
//
#define PREHEAT_1_LABEL      "PLA"
#define PREHEAT_1_TEMP_HOTEND 190
#define PREHEAT_1_TEMP_BED   60
#define PREHEAT_1_TEMP_CHAMBER 35
#define PREHEAT_1_FAN_SPEED   0 // Value from 0 to 255

#define PREHEAT_2_LABEL      "PETG"
#define PREHEAT_2_TEMP_HOTEND 210
#define PREHEAT_2_TEMP_BED   70
#define PREHEAT_2_TEMP_CHAMBER 35
#define PREHEAT_2_FAN_SPEED   0 // Value from 0 to 255


/**
 * Nozzle Park
 *
 * Park the nozzle at the given XYZ position on idle or G27.
 *
 * The "P" parameter controls the action applied to the Z axis:
 *
 * P0 (Default) If Z is below park Z raise the nozzle.
 * P1 Raise the nozzle always to Z-park height.
 * P2 Raise the nozzle by Z-park amount, limited to Z_MAX_POS.
 */
//#define NOZZLE_PARK_FEATURE

#if ENABLED(NOZZLE_PARK_FEATURE)
  // Specify a park position as { X, Y, Z_raise }
  #define NOZZLE_PARK_POINT { (X_MIN_POS + 10), (Y_MAX_POS - 10), 20 }
  //#define NOZZLE_PARK_X_ONLY          // X move only is required to park
  //#define NOZZLE_PARK_Y_ONLY          // Y move only is required to park
  #define NOZZLE_PARK_Z_RAISE_MIN     2 // (mm) Always raise Z by at least this distance
  #define NOZZLE_PARK_XY_FEEDRATE    100 // (mm/s) X and Y axes feedrate (also used for
delta Z axis)
  #define NOZZLE_PARK_Z_FEEDRATE     5 // (mm/s) Z axis feedrate (not used for delta printers)
#endif

/**
 * Clean Nozzle Feature -- EXPERIMENTAL
 *
 * Adds the G12 command to perform a nozzle cleaning process.
 *
 * Parameters:

```


- * P Pattern
- * S Strokes / Repetitions
- * T Triangles (P1 only)
- *
- * Patterns:
- * P0 Straight line (default). This process requires a sponge type material at a fixed bed location. "S" specifies strokes (i.e. back-forth motions) between the start / end points.
- *
- * P1 Zig-zag pattern between (X0, Y0) and (X1, Y1), "T" specifies the number of zig-zag triangles to do. "S" defines the number of strokes. Zig-zags are done in whichever is the narrower dimension. For example, "G12 P1 S1 T3" will execute:



- * P2 Circular pattern with middle at NOZZLE_CLEAN_CIRCLE_MIDDLE. "R" specifies the radius. "S" specifies the stroke count. Before starting, the nozzle moves to NOZZLE_CLEAN_START_POINT.
- *
- * Caveats: The ending Z should be the same as starting Z.
- * Attention: EXPERIMENTAL. G-code arguments may change.
- */

```

//#define NOZZLE_CLEAN_FEATURE

#if ENABLED(NOZZLE_CLEAN_FEATURE)
  // Default number of pattern repetitions
  #define NOZZLE_CLEAN_STROKES 12

  // Default number of triangles
  #define NOZZLE_CLEAN_TRIANGLES 3

  // Specify positions for each tool as { { X, Y, Z }, { X, Y, Z } }
  // Dual hotend system may use { { -20, (Y_BED_SIZE / 2), (Z_MIN_POS + 1) }, { 420,
  (Y_BED_SIZE / 2), (Z_MIN_POS + 1) } }
  #define NOZZLE_CLEAN_START_POINT { { 30, 30, (Z_MIN_POS + 1) } }
  #define NOZZLE_CLEAN_END_POINT { { 100, 60, (Z_MIN_POS + 1) } }

  // Circular pattern radius
  #define NOZZLE_CLEAN_CIRCLE_RADIUS 6.5
  // Circular pattern circle fragments number
  #define NOZZLE_CLEAN_CIRCLE_FN 10
  // Middle point of circle
  #define NOZZLE_CLEAN_CIRCLE_MIDDLE NOZZLE_CLEAN_START_POINT

  // Move the nozzle to the initial position after cleaning
  #define NOZZLE_CLEAN_GOBACK

  // For a purge/clean station that's always at the gantry height (thus no Z move)
  //#define NOZZLE_CLEAN_NO_Z

  // For a purge/clean station mounted on the X axis

```

```

//#define NOZZLE_CLEAN_NO_Y

// Require a minimum hotend temperature for cleaning
#define NOZZLE_CLEAN_MIN_TEMP 170
//#define NOZZLE_CLEAN_HEATUP // Heat up the nozzle instead of skipping wipe

// Explicit wipe G-code script applies to a G12 with no arguments.
//#define WIPE_SEQUENCE_COMMANDS "G1 X-17 Y25 Z10 F4000\nG1 Z1\nM114\nG1 X-17
Y25\nG1 X-17 Y95\nG1 X-17 Y25\nG1 X-17 Y95\nG1 X-17 Y25\nG1 X-17 Y95\nG1 X-17 Y25\nG1
X-17 Y95\nG1 X-17 Y25\nG1 X-17 Y95\nG1 X-17 Y25\nG1 X-17 Y95\nG1 Z15\nM400\nG0 X-10.0
Y-9.0"

#endif

/**
 * Print Job Timer
 *
 * Automatically start and stop the print job timer on M104/M109/M190.
 *
 * M104 (hotend, no wait) - high temp = none, low temp = stop timer
 * M109 (hotend, wait) - high temp = start timer, low temp = stop timer
 * M190 (bed, wait) - high temp = start timer, low temp = none
 *
 * The timer can also be controlled with the following commands:
 *
 * M75 - Start the print job timer
 * M76 - Pause the print job timer
 * M77 - Stop the print job timer
 */
#define PRINTJOB_TIMER_AUTOSTART

/**
 * Print Counter
 *
 * Track statistical data such as:
 *
 * - Total print jobs
 * - Total successful print jobs
 * - Total failed print jobs
 * - Total time printing
 *
 * View the current statistics with M78.
 */
//#define PRINTCOUNTER
#if ENABLED(PRINTCOUNTER)
#define PRINTCOUNTER_SAVE_INTERVAL 60 // (minutes) EEPROM save interval during print
#endif

/**
 * Password
 *
 * Set a numerical password for the printer which can be requested:
 *
 * - When the printer boots up
 * - Upon opening the 'Print from Media' Menu
 * - When SD printing is completed or aborted
 *
 * The following G-codes can be used:
 *
 * M510 - Lock Printer. Blocks all commands except M511.

```

```

* M511 - Unlock Printer.
* M512 - Set, Change and Remove Password.
*
* If you forget the password and get locked out you'll need to re-flash
* the firmware with the feature disabled, reset EEPROM, and (optionally)
* re-flash the firmware again with this feature enabled.
*/
#define PASSWORD_FEATURE
#if ENABLED(PASSWORD_FEATURE)
  #define PASSWORD_LENGTH 4          // (#) Number of digits (1-9). 3 or 4 is recommended
  #define PASSWORD_ON_STARTUP
  #define PASSWORD_UNLOCK_GCODE     // Unlock with the M511 P<password>
command. Disable to prevent brute-force attack.
  #define PASSWORD_CHANGE_GCODE     // Change the password with M512 P<old>
S<new>.
  //#define PASSWORD_ON_SD_PRINT_MENU // This does not prevent gcodes from running
  //#define PASSWORD_AFTER_SD_PRINT_END
  //#define PASSWORD_AFTER_SD_PRINT_ABORT
  //#include "Configuration_Secure.h" // External file with PASSWORD_DEFAULT_VALUE
#endif

//
=====
====
//===== LCD and SD support
=====
//
=====
====

// @section lcd

/**
 * LCD LANGUAGE
 *
 * Select the language to display on the LCD. These languages are available:
 *
 * en, an, bg, ca, cz, da, de, el, el_gr, es, eu, fi, fr, gl, hr, hu, it,
 * jp_kana, ko_KR, nl, pl, pt, pt_br, ro, ru, sk, sv, tr, uk, vi, zh_CN, zh_TW
 *
 * :{ 'en':'English', 'an':'Aragonese', 'bg':'Bulgarian', 'ca':'Catalan', 'cz':'Czech', 'da':'Danish',
'de':'German', 'el':'Greek', 'el_gr':'Greek (Greece)', 'es':'Spanish', 'eu':'Basque-Euskera',
'fi':'Finnish', 'fr':'French', 'gl':'Galician', 'hr':'Croatian', 'hu':'Hungarian', 'it':'Italian',
'jp_kana':'Japanese', 'ko_KR':'Korean (South Korea)', 'nl':'Dutch', 'pl':'Polish', 'pt':'Portuguese',
'pt_br':'Portuguese (Brazilian)', 'ro':'Romanian', 'ru':'Russian', 'sk':'Slovak', 'sv':'Swedish',
'tr':'Turkish', 'uk':'Ukrainian', 'vi':'Vietnamese', 'zh_CN':'Chinese (Simplified)', 'zh_TW':'Chinese
(Traditional)' }
 */
#define LCD_LANGUAGE en

/**
 * LCD Character Set
 *
 * Note: This option is NOT applicable to Graphical Displays.
 *
 * All character-based LCDs provide ASCII plus one of these
 * language extensions:
 *
 * - JAPANESE ... the most common
 * - WESTERN ... with more accented characters

```

```

* - CYRILLIC ... for the Russian language
*
* To determine the language extension installed on your controller:
*
* - Compile and upload with LCD_LANGUAGE set to 'test'
* - Click the controller to view the LCD menu
* - The LCD will display Japanese, Western, or Cyrillic text
*
* See https://marlinfw.org/docs/development/lcd\_language.html
*
* :['JAPANESE', 'WESTERN', 'CYRILLIC']
*/
#define DISPLAY_CHARSET_HD44780 JAPANESE

/**
 * Info Screen Style (0:Classic, 1:Průša)
 *
 * :[0:'Classic', 1:'Průša']
 */
#define LCD_INFO_SCREEN_STYLE 0

/**
 * SD CARD
 *
 * SD Card support is disabled by default. If your controller has an SD slot,
 * you must uncomment the following option or it won't work.
 */
#define SDSUPPORT

/**
 * SD CARD: ENABLE CRC
 *
 * Use CRC checks and retries on the SD communication.
 */
// #define SD_CHECK_AND_RETRY

/**
 * LCD Menu Items
 *
 * Disable all menus and only display the Status Screen, or
 * just remove some extraneous menu items to recover space.
 */
// #define NO_LCD_MENUS
// #define SLIM_LCD_MENUS

//
// ENCODER SETTINGS
//
// This option overrides the default number of encoder pulses needed to
// produce one step. Should be increased for high-resolution encoders.
//
// #define ENCODER_PULSES_PER_STEP 4

//
// Use this option to override the number of step signals required to
// move between next/prev menu items.
//
// #define ENCODER_STEPS_PER_MENU_ITEM 1

/**

```

```

* Encoder Direction Options
*
* Test your encoder's behavior first with both options disabled.
*
* Reversed Value Edit and Menu Nav? Enable REVERSE_ENCODER_DIRECTION.
* Reversed Menu Navigation only? Enable REVERSE_MENU_DIRECTION.
* Reversed Value Editing only? Enable BOTH options.
*/

//
// This option reverses the encoder direction everywhere.
//
// Set this option if CLOCKWISE causes values to DECREASE
//
//#define REVERSE_ENCODER_DIRECTION

//
// This option reverses the encoder direction for navigating LCD menus.
//
// If CLOCKWISE normally moves DOWN this makes it go UP.
// If CLOCKWISE normally moves UP this makes it go DOWN.
//
//#define REVERSE_MENU_DIRECTION

//
// This option reverses the encoder direction for Select Screen.
//
// If CLOCKWISE normally moves LEFT this makes it go RIGHT.
// If CLOCKWISE normally moves RIGHT this makes it go LEFT.
//
//#define REVERSE_SELECT_DIRECTION

//
// Individual Axis Homing
//
// Add individual axis homing items (Home X, Home Y, and Home Z) to the LCD menu.
//
//#define INDIVIDUAL_AXIS_HOMING_MENU

//
// SPEAKER/BUZZER
//
// If you have a speaker that can produce tones, enable it here.
// By default Marlin assumes you have a buzzer with a fixed frequency.
//
//#define SPEAKER

//
// The duration and frequency for the UI feedback sound.
// Set these to 0 to disable audio feedback in the LCD menus.
//
// Note: Test audio output with the G-Code:
// M300 S<frequency Hz> P<duration ms>
//
//#define LCD_FEEDBACK_FREQUENCY_DURATION_MS 2
//#define LCD_FEEDBACK_FREQUENCY_HZ 5000

//
=====
=====

```

```

//===== LCD / Controller Selection =====
//===== (Character-based LCDs) =====
//
=====
=====

//
// RepRapDiscount Smart Controller.
// https://reprap.org/wiki/RepRapDiscount_Smart_Controller
//
// Note: Usually sold with a white PCB.
//
#define REPRAP_DISCOUNT_SMART_CONTROLLER

//
// GT2560 (YHCB2004) LCD Display
//
// Requires Testato, Koepel softwarewire library and
// Andriy Golovnya's LiquidCrystal_AIP31068 library.
//
//#define YHCB2004

//
// Original RADDs LCD Display+Encoder+SDCardReader
// http://doku.radds.org/dokumentation/lcd-display/
//
//#define RADDs_DISPLAY

//
// ULTIMAKER Controller.
//
//#define ULTIMAKERCONTROLLER

//
// ULTIPANEL as seen on Thingiverse.
//
//#define ULTIPANEL

//
// PanelOne from T3P3 (via RAMPS 1.4 AUX2/AUX3)
// https://reprap.org/wiki/PanelOne
//
//#define PANEL_ONE

//
// GADGETS3D G3D LCD/SD Controller
// https://reprap.org/wiki/RAMPS_1.3/1.4_GADGETS3D_Shield_with_Panel
//
// Note: Usually sold with a blue PCB.
//
//#define G3D_PANEL

//
// RigidBot Panel V1.0
// http://www.inventapart.com/
//
//#define RIGIDBOT_PANEL

//
// Makeboard 3D Printer Parts 3D Printer Mini Display 1602 Mini Controller

```

```

// https://www.aliexpress.com/item/32765887917.html
//
// #define MAKEBOARD_MINI_2_LINE_DISPLAY_1602

//
// ANET and Tronxy 20x4 Controller
//
// #define ZONESTAR_LCD // Requires ADC_KEYPAD_PIN to be assigned to an analog pin.
// This LCD is known to be susceptible to electrical interference
// which scrambles the display. Pressing any button clears it up.
// This is a LCD2004 display with 5 analog buttons.

//
// Generic 16x2, 16x4, 20x2, or 20x4 character-based LCD.
//
// #define ULTRA_LCD

//
=====
====
// ===== LCD / Controller Selection =====
// ===== (I2C and Shift-Register LCDs) =====
//
=====
====

//
// CONTROLLER TYPE: I2C
//
// Note: These controllers require the installation of Arduino's LiquidCrystal_I2C
// library. For more info: https://github.com/kiyoshigawa/LiquidCrystal_I2C
//

//
// Elefu RA Board Control Panel
// http://www.elefu.com/index.php?route=product/product&product_id=53
//
// #define RA_CONTROL_PANEL

//
// Sainsmart (YwRobot) LCD Displays
//
// These require F.Malpartida's LiquidCrystal_I2C library
// https://bitbucket.org/fmalpartida/new-liquidcrystal/wiki/Home
//
// #define LCD_SAINSMART_I2C_1602
// #define LCD_SAINSMART_I2C_2004

//
// Generic LCM1602 LCD adapter
//
// #define LCM1602

//
// PANELOLU2 LCD with status LEDs,
// separate encoder and click inputs.
//
// Note: This controller requires Arduino's LiquidTWI2 library v1.2.3 or later.
// For more info: https://github.com/lincomatic/LiquidTWI2
//

```

```

// Note: The PANELOLU2 encoder click input can either be directly connected to
// a pin (if BTN_ENC defined to != -1) or read through I2C (when BTN_ENC == -1).
//
//#define LCD_I2C_PANELOLU2

//
// Panucatt VIKI LCD with status LEDs,
// integrated click & L/R/U/D buttons, separate encoder inputs.
//
//#define LCD_I2C_VIKI

//
// CONTROLLER TYPE: Shift register panels
//

//
// 2-wire Non-latching LCD SR from https://goo.gl/aJJ4sH
// LCD configuration: https://reprap.org/wiki/SAV_3D_LCD
//
//#define SAV_3DLCD

//
// 3-wire SR LCD with strobe using 74HC4094
// https://github.com/mikeshub/SailfishLCD
// Uses the code directly from Sailfish
//
//#define FF_INTERFACEBOARD

//
// TFT GLCD Panel with Marlin UI
// Panel connected to main board by SPI or I2C interface.
// See https://github.com/Serhiy-K/TFTGLCDAdapter
//
//#define TFTGLCD_PANEL_SPI
//#define TFTGLCD_PANEL_I2C

//
=====
====
//===== LCD / Controller Selection =====
//===== (Graphical LCDs) =====
//
=====
====

//
// CONTROLLER TYPE: Graphical 128x64 (DOGM)
//
// IMPORTANT: The U8glib library is required for Graphical Display!
// https://github.com/olikraus/U8glib_Arduino
//
// NOTE: If the LCD is unresponsive you may need to reverse the plugs.
//

//
// RepRapDiscount FULL GRAPHIC Smart Controller
// https://reprap.org/wiki/RepRapDiscount_Full_Graphic_Smart_Controller
//
//#define REPRAP_DISCOUNT_FULL_GRAPHIC_SMART_CONTROLLER

```



```
//  
// K.3D Full Graphic Smart Controller  
//  
// #define K3D_FULL_GRAPHIC_SMART_CONTROLLER  
  
//  
// ReprapWorld Graphical LCD  
// https://reprapworld.com/?products\_details&products\_id/1218  
//  
// #define REPRAPWORLD_GRAPHICAL_LCD  
  
//  
// Activate one of these if you have a Panucatt Devices  
// Viki 2.0 or mini Viki with Graphic LCD  
// https://www.panucatt.com  
//  
// #define VIKI2  
// #define miniVIKI  
  
//  
// MakerLab Mini Panel with graphic  
// controller and SD support - https://reprap.org/wiki/Mini\_panel  
//  
// #define MINIPANEL  
  
//  
// MaKr3d Makr-Panel with graphic controller and SD support.  
// https://reprap.org/wiki/MaKr3d\_MaKrPanel  
//  
// #define MAKRPANEL  
  
//  
// Adafruit ST7565 Full Graphic Controller.  
// https://github.com/eboston/Adafruit-ST7565-Full-Graphic-Controller/  
//  
// #define ELB_FULL_GRAPHIC_CONTROLLER  
  
//  
// BQ LCD Smart Controller shipped by  
// default with the BQ Hephestos 2 and Witbox 2.  
//  
// #define BQ_LCD_SMART_CONTROLLER  
  
//  
// Cartesio UI  
// http://mauk.cc/webshop/cartesio-shop/electronics/user-interface  
//  
// #define CARTESIO_UI  
  
//  
// LCD for Melzi Card with Graphical LCD  
//  
// #define LCD_FOR_MELZI  
  
//  
// Original Ulticontroller from Ultimaker 2 printer with SSD1309 I2C display and encoder  
// https://github.com/Ultimaker/Ultimaker2/tree/master/1249\_Ulticontroller\_Board\_\(x1\)  
//  
// #define ULTI_CONTROLLER
```

```
//  
// MKS MINI12864 with graphic controller and SD support  
// https://reprap.org/wiki/MKS\_MINI\_12864  
//  
// #define MKS_MINI_12864  
  
//  
// MKS LCD12864A/B with graphic controller and SD support. Follows MKS_MINI_12864 pinout.  
// https://www.aliexpress.com/item/33018110072.html  
//  
// #define MKS_LCD12864  
  
//  
// FYSETC variant of the MINI12864 graphic controller with SD support  
// https://wiki.fysetc.com/Mini12864\_Panel/  
//  
// #define FYSETC_MINI_12864_X_X // Type C/D/E/F. No tunable RGB Backlight by default  
// #define FYSETC_MINI_12864_1_2 // Type C/D/E/F. Simple RGB Backlight (always on)  
// #define FYSETC_MINI_12864_2_0 // Type A/B. Discreet RGB Backlight  
// #define FYSETC_MINI_12864_2_1 // Type A/B. NeoPixel RGB Backlight  
// #define FYSETC_GENERIC_12864_1_1 // Larger display with basic ON/OFF backlight.  
  
//  
// Factory display for Creality CR-10  
// https://www.aliexpress.com/item/32833148327.html  
//  
// This is RAMPS-compatible using a single 10-pin connector.  
// (For CR-10 owners who want to replace the Melzi Creality board but retain the display)  
//  
// #define CR10_STOCKDISPLAY  
  
//  
// Ender-2 OEM display, a variant of the MKS_MINI_12864  
//  
// #define ENDER2_STOCKDISPLAY  
  
//  
// ANET and Tronxy Graphical Controller  
//  
// Anet 128x64 full graphics lcd with rotary encoder as used on Anet A6  
// A clone of the RepRapDiscount full graphics display but with  
// different pins/wiring (see pins_ANET_10.h). Enable one of these.  
//  
// #define ANET_FULL_GRAPHICS_LCD  
// #define ANET_FULL_GRAPHICS_LCD_ALT_WIRING  
  
//  
// AZSMZ 12864 LCD with SD  
// https://www.aliexpress.com/item/32837222770.html  
//  
// #define AZSMZ_12864  
  
//  
// Silvergate GLCD controller  
// https://github.com/android444/Silvergate  
//  
// #define SILVER_GATE_GLCD_CONTROLLER
```

```

//
=====
====
//===== OLED Displays
=====
//
=====
====

//
// SSD1306 OLED full graphics generic display
//
//#define U8GLIB_SSD1306

//
// SAV OLEd LCD module support using either SSD1306 or SH1106 based LCD modules
//
//#define SAV_3DGLCD
#if ENABLED(SAV_3DGLCD)
  #define U8GLIB_SSD1306
  // #define U8GLIB_SH1106
#endif

//
// TinyBoy2 128x64 OLED / Encoder Panel
//
//#define OLED_PANEL_TINYBOY2

//
// MKS OLED 1.3" 128x64 Full Graphics Controller
// https://reprap.org/wiki/MKS\_12864OLED
//
// Tiny, but very sharp OLED display
//
//#define MKS_12864OLED // Uses the SH1106 controller (default)
// #define MKS_12864OLED_SSD1306 // Uses the SSD1306 controller

//
// Zonestar OLED 128x64 Full Graphics Controller
//
// #define ZONESTAR_12864LCD // Graphical (DOGM) with ST7920 controller
// #define ZONESTAR_12864OLED // 1.3" OLED with SH1106 controller (default)
// #define ZONESTAR_12864OLED_SSD1306 // 0.96" OLED with SSD1306 controller

//
// Einstart S OLED SSD1306
//
// #define U8GLIB_SH1106_EINSTART

//
// Overlord OLED display/controller with i2c buzzer and LEDs
//
// #define OVERLORD_OLED

//
// FYSETC OLED 2.42" 128x64 Full Graphics Controller with WS2812 RGB
// Where to find : https://www.aliexpress.com/item/4000345255731.html
// #define FYSETC_242_OLED_12864 // Uses the SSD1309 controller

//

```

```

// K.3D SSD1309 OLED 2.42" 128x64 Full Graphics Controller
//
// #define K3D_242_OLED_CONTROLLER // Software SPI

//
=====
====
// ===== Extensible UI Displays =====
//
=====
====

//
// DGUS Touch Display with DWIN OS. (Choose one.)
// ORIGIN : https://www.aliexpress.com/item/32993409517.html
// FYSETC : https://www.aliexpress.com/item/32961471929.html
//
// #define DGUS_LCD_UI_ORIGIN
// #define DGUS_LCD_UI_FYSETC
// #define DGUS_LCD_UI_HIPRECY
// #define DGUS_LCD_UI_MKS

//
// Touch-screen LCD for Malyan M200/M300 printers
//
// #define MALYAN_LCD
// #if ENABLED(MALYAN_LCD)
//   #define LCD_SERIAL_PORT 1 // Default is 1 for Malyan M200
// #endif

//
// Touch UI for FTDI EVE (FT800/FT810) displays
// See Configuration_adv.h for all configuration options.
//
// #define TOUCH_UI_FTDI_EVE

//
// Touch-screen LCD for Anycubic printers
//
// #define ANYCUBIC_LCD_I3MEGA
// #define ANYCUBIC_LCD_CHIRON
// #if EITHER(ANYCUBIC_LCD_I3MEGA, ANYCUBIC_LCD_CHIRON)
//   #define LCD_SERIAL_PORT 3 // Default is 3 for Anycubic
//   #define ANYCUBIC_LCD_DEBUG
// #endif

//
// 320x240 Nextion 2.8" serial TFT Resistive Touch Screen NX3224T028
//
// #define NEXTION_TFT
// #if ENABLED(NEXTION_TFT)
//   #define LCD_SERIAL_PORT 1 // Default is 1 for Nextion
// #endif

//
// Third-party or vendor-customized controller interfaces.
// Sources should be installed in 'src/lcd/extui'.
//
// #define EXTENSIBLE_UI

```

```
#if ENABLED(EXTENSIBLE_UI)
  //#define EXTUI_LOCAL_BEEPER // Enables use of local Beeper pin with external display
#endif

//
=====
====
//===== Graphical TFTs
=====
//
=====
====

/**
 * Specific TFT Model Presets. Enable one of the following options
 * or enable TFT_GENERIC and set sub-options.
 */

//
// 480x320, 3.5", SPI Display From MKS
// Normally used in MKS Robin Nano V2
//
//#define MKS_TS35_V2_0

//
// 320x240, 2.4", FSMC Display From MKS
// Normally used in MKS Robin Nano V1.2
//
//#define MKS_ROBIN_TFT24

//
// 320x240, 2.8", FSMC Display From MKS
// Normally used in MKS Robin Nano V1.2
//
//#define MKS_ROBIN_TFT28

//
// 320x240, 3.2", FSMC Display From MKS
// Normally used in MKS Robin Nano V1.2
//
//#define MKS_ROBIN_TFT32

//
// 480x320, 3.5", FSMC Display From MKS
// Normally used in MKS Robin Nano V1.2
//
//#define MKS_ROBIN_TFT35

//
// 480x272, 4.3", FSMC Display From MKS
//
//#define MKS_ROBIN_TFT43

//
// 320x240, 3.2", FSMC Display From MKS
// Normally used in MKS Robin
//
//#define MKS_ROBIN_TFT_V1_1R

//
```

```

// 480x320, 3.5", FSMC Stock Display from TronxXY
//
//#define TFT_TRONXY_X5SA

//
// 480x320, 3.5", FSMC Stock Display from AnyCubic
//
//#define ANYCUBIC_TFT35

//
// 320x240, 2.8", FSMC Stock Display from Longer/Alfawise
//
//#define LONGER_LK_TFT28

//
// 320x240, 2.8", FSMC Stock Display from ET4
//
//#define ANET_ET4_TFT28

//
// 480x320, 3.5", FSMC Stock Display from ET5
//
//#define ANET_ET5_TFT35

//
// Generic TFT with detailed options
//
//#define TFT_GENERIC
#if ENABLED(TFT_GENERIC)
  // :[ 'AUTO', 'ST7735', 'ST7789', 'ST7796', 'R61505', 'ILI9328', 'ILI9341', 'ILI9488' ]
  #define TFT_DRIVER AUTO

  // Interface. Enable one of the following options:
  //#define TFT_INTERFACE_FSMC
  //#define TFT_INTERFACE_SPI

  // TFT Resolution. Enable one of the following options:
  //#define TFT_RES_320x240
  //#define TFT_RES_480x272
  //#define TFT_RES_480x320
#endif

/**
 * TFT UI - User Interface Selection. Enable one of the following options:
 *
 * TFT_CLASSIC_UI - Emulated DOGM - 128x64 Upscaled
 * TFT_COLOR_UI - Marlin Default Menus, Touch Friendly, using full TFT capabilities
 * TFT_LVGL_UI - A Modern UI using LVGL
 *
 * For LVGL_UI also copy the 'assets' folder from the build directory to the
 * root of your SD card, together with the compiled firmware.
 */
//#define TFT_CLASSIC_UI
//#define TFT_COLOR_UI
//#define TFT_LVGL_UI

#if ENABLED(TFT_LVGL_UI)
  //#define MKS_WIFI_MODULE // MKS WiFi module
#endif

```

```

/**
 * TFT Rotation. Set to one of the following values:
 *
 * TFT_ROTATE_90, TFT_ROTATE_90_MIRROR_X, TFT_ROTATE_90_MIRROR_Y,
 * TFT_ROTATE_180, TFT_ROTATE_180_MIRROR_X, TFT_ROTATE_180_MIRROR_Y,
 * TFT_ROTATE_270, TFT_ROTATE_270_MIRROR_X, TFT_ROTATE_270_MIRROR_Y,
 * TFT_MIRROR_X, TFT_MIRROR_Y, TFT_NO_ROTATION
 */
#define TFT_ROTATION TFT_NO_ROTATION

//
=====
====
//===== Other Controllers =====
//
=====
====

//
// Ender-3 v2 OEM display. A DWIN display with Rotary Encoder.
//
#define DWIN_CREALITY_LCD

//
// ADS7843/XPT2046 ADC Touchscreen such as ILI9341 2.8
//
#define TOUCH_SCREEN
#if ENABLED(TOUCH_SCREEN)
  #define BUTTON_DELAY_EDIT 50 // (ms) Button repeat delay for edit screens
  #define BUTTON_DELAY_MENU 250 // (ms) Button repeat delay for menus

  #define TOUCH_SCREEN_CALIBRATION

  //#define TOUCH_CALIBRATION_X 12316
  //#define TOUCH_CALIBRATION_Y -8981
  //#define TOUCH_OFFSET_X -43
  //#define TOUCH_OFFSET_Y 257
  //#define TOUCH_ORIENTATION TOUCH_LANDSCAPE

  #if BOTH(TOUCH_SCREEN_CALIBRATION, EEPROM_SETTINGS)
    #define TOUCH_CALIBRATION_AUTO_SAVE // Auto save successful calibration values to
EEPROM
  #endif

  #if ENABLED(TFT_COLOR_UI)
    //#define SINGLE_TOUCH_NAVIGATION
  #endif
#endif

//
// RepRapWorld REPRAPWORLD_KEYPAD v1.1
// https://reprapworld.com/products/electronics/ramps/keypad\_v1\_0\_fully\_assembled/
//
#define REPRAPWORLD_KEYPAD
#define REPRAPWORLD_KEYPAD_MOVE_STEP 10.0 // (mm) Distance to move per key-press

//
=====
====

```

```

//===== Extra Features
=====
//
=====
=====

// @section extras

// Set number of user-controlled fans. Disable to use all board-defined fans.
// :[1,2,3,4,5,6,7,8]
// #define NUM_M106_FANS 1

// Increase the FAN PWM frequency. Removes the PWM noise but increases heating in the FET/
// Arduino
// #define FAST_PWM_FAN

// Use software PWM to drive the fan, as for the heaters. This uses a very low frequency
// which is not as annoying as with the hardware PWM. On the other hand, if this frequency
// is too low, you should also increment SOFT_PWM_SCALE.
// #define FAN_SOFT_PWM

// Incrementing this by 1 will double the software PWM frequency,
// affecting heaters, and the fan if FAN_SOFT_PWM is enabled.
// However, control resolution will be halved for each increment;
// at zero value, there are 128 effective control positions.
// :[0,1,2,3,4,5,6,7]
// #define SOFT_PWM_SCALE 0

// If SOFT_PWM_SCALE is set to a value higher than 0, dithering can
// be used to mitigate the associated resolution loss. If enabled,
// some of the PWM cycles are stretched so on average the desired
// duty cycle is attained.
// #define SOFT_PWM_DITHER

// Temperature status LEDs that display the hotend and bed temperature.
// If all hotends, bed temperature, and target temperature are under 54C
// then the BLUE led is on. Otherwise the RED led is on. (1C hysteresis)
// #define TEMP_STAT_LEDS

// Support for the BariCUDA Paste Extruder
// #define BARICUDA

// Support for BlinkM/CyzRgb
// #define BLINKM

// Support for PCA9632 PWM LED driver
// #define PCA9632

// Support for PCA9533 PWM LED driver
// #define PCA9533

/**
 * RGB LED / LED Strip Control
 *
 * Enable support for an RGB LED connected to 5V digital pins, or
 * an RGB Strip connected to MOSFETs controlled by digital pins.
 *
 * Adds the M150 command to set the LED (or LED strip) color.
 * If pins are PWM capable (e.g., 4, 5, 6, 11) then a range of
 * luminance values can be set from 0 to 255.

```



```

* For NeoPixel LED an overall brightness parameter is also available.
*
* *** CAUTION ***
* LED Strips require a MOSFET Chip between PWM lines and LEDs,
* as the Arduino cannot handle the current the LEDs will require.
* Failure to follow this precaution can destroy your Arduino!
* NOTE: A separate 5V power supply is required! The NeoPixel LED needs
* more current than the Arduino 5V linear regulator can produce.
* *** CAUTION ***
*
* LED Type. Enable only one of the following two options.
*/
#define RGB_LED
#define RGBW_LED

#if EITHER(RGB_LED, RGBW_LED)
  #define RGB_LED_R_PIN 34
  #define RGB_LED_G_PIN 43
  #define RGB_LED_B_PIN 35
  #define RGB_LED_W_PIN -1
#endif

// Support for Adafruit NeoPixel LED driver
#define NEOPIXEL_LED
#if ENABLED(NEOPIXEL_LED)
  #define NEOPIXEL_TYPE NEO_GRBW // NEO_GRBW / NEO_GRB - four/three channel driver
  type (defined in Adafruit_NeoPixel.h)
  #define NEOPIXEL_PIN 4 // LED driving pin
  #define NEOPIXEL2_TYPE NEOPIXEL_TYPE
  #define NEOPIXEL2_PIN 5
  #define NEOPIXEL_PIXELS 30 // Number of LEDs in the strip. (Longest strip when
  NEOPIXEL2_SEPARATE is disabled.)
  #define NEOPIXEL_IS_SEQUENTIAL // Sequential display for temperature change - LED by
  LED. Disable to change all LEDs at once.
  #define NEOPIXEL_BRIGHTNESS 127 // Initial brightness (0-255)
  #define NEOPIXEL_STARTUP_TEST // Cycle through colors at startup

  // Support for second Adafruit NeoPixel LED driver controlled with M150 S1 ...
  #define NEOPIXEL2_SEPARATE
  #if ENABLED(NEOPIXEL2_SEPARATE)
    #define NEOPIXEL2_PIXELS 15 // Number of LEDs in the second strip
    #define NEOPIXEL2_BRIGHTNESS 127 // Initial brightness (0-255)
    #define NEOPIXEL2_STARTUP_TEST // Cycle through colors at startup
  #else
    #define NEOPIXEL2_INSERTIES // Default behavior is NeoPixel 2 in parallel
  #endif

  // Use a single NeoPixel LED for static (background) lighting
  #define NEOPIXEL_BKGD_LED_INDEX 0 // Index of the LED to use
  #define NEOPIXEL_BKGD_COLOR { 255, 255, 255, 0 } // R, G, B, W
  #define NEOPIXEL_BKGD_ALWAYS_ON // Keep the backlight on when other
  NeoPixels are off
#endif

/**
* Printer Event LEDs
*
* During printing, the LEDs will reflect the printer status:
*
* - Gradually change from blue to violet as the heated bed gets to target temp

```

```

* - Gradually change from violet to red as the hotend gets to temperature
* - Change to white to illuminate work surface
* - Change to green once print has finished
* - Turn off after the print has finished and the user has pushed a button
*/
#if ANY(BLINKM, RGB_LED, RGBW_LED, PCA9632, PCA9533, NEOPIXEL_LED)
  #define PRINTER_EVENT_LEDS
#endif

/**
 * Number of servos
 *
 * For some servo-related options NUM_SERVOS will be set automatically.
 * Set this manually if there are extra servos needing manual control.
 * Set to 0 to turn off servo support.
 */
// #define NUM_SERVOS 3 // Servo index starts with 0 for M280 command

// (ms) Delay before the next move will start, to give the servo time to reach its target angle.
// 300ms is a good value but you can try less delay.
// If the servo can't reach the requested position, increase it.
#define SERVO_DELAY { 300 }

// Only power servos during movement, otherwise leave off to prevent jitter
// #define DEACTIVATE_SERVOS_AFTER_MOVE

// Edit servo angles with M281 and save to EEPROM with M500
// #define EDITABLE_SERVO_ANGLES

```